



# USER GUIDE

v2022.1.1 | March 2022

**User Manual**



# TABLE OF CONTENTS

<b>Chapter 1. Profiling from the CLI.....</b>	<b>1</b>
1.1. Installing the CLI on Your Target.....	1
1.2. Command Line Options.....	1
1.2.1. CLI Global Options.....	2
1.3. CLI Command Switches.....	2
1.3.1. CLI Profile Command Switch Options.....	3
1.3.2. CLI Start Command Switch Options.....	29
1.3.3. CLI Stop Command Switch Options.....	43
1.3.4. CLI Cancel Command Switch Options.....	44
1.3.5. CLI Launch Command Switch Options.....	45
1.3.6. CLI Shutdown Command Switch Options.....	58
1.3.7. CLI Export Command Switch Options.....	59
1.3.8. CLI Stats Command Switch Options.....	60
1.3.9. CLI Analyze Command Switch Options.....	65
1.3.10. CLI Status Command Switch Options.....	67
1.3.11. CLI Sessions Command Switch Subcommands.....	68
1.4. Example Single Command Lines.....	68
1.5. Example Interactive CLI Command Sequences.....	71
1.6. Example Stats Command Sequences.....	76
1.7. Example Output from --stats Option.....	77
1.8. Importing and Viewing Command Line Results Files.....	80
1.9. Using the CLI to Analyze MPI Codes.....	82
1.9.1. Tracing MPI API calls.....	82
1.9.2. Using the CLI to Profile Applications Launched with mpirun.....	82
<b>Chapter 2. Profiling from the GUI.....</b>	<b>85</b>
2.1. Profiling Linux Targets from the GUI.....	85
2.1.1. Connecting to the Target Device.....	85
2.1.2. System-Wide Profiling Options.....	87
2.1.2.1. Linux x86_64.....	87
2.1.2.2. Linux for Tegra.....	89
2.1.3. Target Sampling Options.....	89
Target Sampling Options for Workstation.....	89
Target Sampling Options for Embedded Linux.....	90
2.1.4. Hotkey Trace Start/Stop.....	91
2.1.5. Launching and Attaching to Processes.....	91
2.2. Profiling Windows Targets from the GUI.....	92
Remoting to a Windows Based Machine.....	92
Hotkey Trace Start/Stop.....	92
Target Sampling Options on Windows.....	93
Symbol Locations.....	94

2.3. Profiling QNX Targets from the GUI.....	95
<b>Chapter 3. Export Formats.....</b>	<b>96</b>
3.1. SQLite Schema Reference.....	96
3.2. SQLite Schema Event Values.....	98
3.3. Common SQLite Examples.....	104
3.4. Arrow Format Description.....	118
3.5. JSON and Text Format Description.....	119
<b>Chapter 4. Report Scripts.....</b>	<b>120</b>
Report Scripts Shipped With Nsight Systems.....	120
apigpusum[:base] -- CUDA API & GPU Summary (CUDA API + kernels + memory ops).....	120
cudaapisum -- CUDA API Summary.....	121
cudaapitrace -- CUDA API Trace.....	121
gpukernsum[:base] -- CUDA GPU Kernel Summary.....	121
gpumemsizesum -- GPU Memory Operations Summary (by Size).....	122
gpumemtimesum -- GPU Memory Operations Summary (by Time).....	122
gpusum[:base] -- GPU Summary (kernels + memory operations).....	123
gputrace -- CUDA GPU Trace.....	123
nvtxppsum -- NVTX Push/Pop Range Summary.....	124
openmpevtsum -- OpenMP Event Summary.....	124
osrtsum -- OS Runtime Summary.....	124
vulkanmarkerssum -- Vulkan Range Summary.....	125
pixsum -- PIX Range Summary.....	125
khrdebugsum -- OpenGL KHR_debug Range Summary.....	126
Report Formatters Shipped With Nsight Systems.....	126
Column.....	126
Table.....	127
CSV.....	127
TSV.....	128
JSON.....	128
HDoc.....	128
HTable.....	129
<b>Chapter 5. Migrating from NVIDIA nvprof.....</b>	<b>130</b>
Using the Nsight Systems CLI nvprof Command.....	130
CLI nvprof Command Switch Options.....	130
Next Steps.....	133
<b>Chapter 6. Profiling in a Docker on Linux Devices.....</b>	<b>134</b>
<b>Chapter 7. Direct3D Trace.....</b>	<b>136</b>
7.1. D3D11 API trace.....	136
7.2. D3D12 API Trace.....	136
<b>Chapter 8. WDDM Queues.....</b>	<b>141</b>
<b>Chapter 9. Vulkan API Trace.....</b>	<b>143</b>
9.1. Vulkan Overview.....	143
9.2. Pipeline Creation Feedback.....	144

9.3. Vulkan GPU Trace Notes.....	145
<b>Chapter 10. Stutter Analysis.....</b>	<b>146</b>
10.1. FPS Overview.....	146
10.2. Frame Health.....	149
10.3. GPU Memory Utilization.....	150
10.4. Vertical Synchronization.....	150
<b>Chapter 11. OpenMP Trace.....</b>	<b>151</b>
<b>Chapter 12. OS Runtime Libraries Trace.....</b>	<b>153</b>
12.1. Locking a Resource.....	154
12.2. Limitations.....	154
12.3. OS Runtime Libraries Trace Filters.....	155
12.4. OS Runtime Default Function List.....	156
<b>Chapter 13. NVTX Trace.....</b>	<b>159</b>
<b>Chapter 14. CUDA Trace.....</b>	<b>163</b>
14.1. CUDA GPU Memory Allocation Graph.....	166
14.2. Unified Memory Transfer Trace.....	166
Unified Memory CPU Page Faults.....	168
Unified Memory GPU Page Faults.....	169
14.3. CUDA Default Function List for CLI.....	171
14.4. cuDNN Function List for X86 CLI.....	173
<b>Chapter 15. OpenACC Trace.....</b>	<b>175</b>
<b>Chapter 16. OpenGL Trace.....</b>	<b>177</b>
16.1. OpenGL Trace Using Command Line.....	179
<b>Chapter 17. Custom ETW Trace.....</b>	<b>181</b>
<b>Chapter 18. GPU Metric Sampling.....</b>	<b>183</b>
Overview.....	183
Launching GPU Metric Sampling from the CLI.....	184
Launching GPU Metric Sampling from the GUI.....	185
Sampling frequency.....	185
Available Metrics.....	186
Exporting and Querying Data.....	189
Limitations.....	190
<b>Chapter 19. NVIDIA Video Codec SDK Trace.....</b>	<b>191</b>
19.1. NV Encoder API Functions Traced by Default.....	192
19.2. NV Decoder API Functions Traced by Default.....	193
19.3. NV JPEG API Functions Traced by Default.....	194
<b>Chapter 20. Network Communication Profiling.....</b>	<b>195</b>
20.1. MPI API Trace.....	196
20.2. OpenSHMEM Library Trace.....	199
20.3. UCX Library Trace.....	199
20.4. NVIDIA NVSHMEM and NCCL Trace.....	200
20.5. NIC Metric Sampling.....	201
<b>Chapter 21. Reading Your Report in GUI.....</b>	<b>203</b>

21.1. Generating a New Report.....	203
21.2. Opening an Existing Report.....	203
21.3. Sharing a Report File.....	203
21.4. Report Tab.....	203
21.5. Analysis Summary View.....	204
21.6. Timeline View.....	204
21.6.1. Timeline.....	204
Row Height.....	205
21.6.2. Events View.....	205
21.6.3. Function Table Modes.....	207
21.6.4. Filter Dialog.....	210
21.7. Diagnostics Summary View.....	210
21.8. Symbol Resolution Logs View.....	211
<b>Chapter 22. Adding Report to the Timeline.....</b>	<b>212</b>
22.1. Time Synchronization.....	212
22.2. Timeline Hierarchy.....	214
22.3. Example: MPI.....	215
22.4. Limitations.....	216
<b>Chapter 23. Using Nsight Systems Expert System.....</b>	<b>217</b>
Using Expert System from the CLI.....	217
Using Expert System from the GUI.....	217
Expert System Rules.....	218
CUDA Synchronous Operation Rules.....	218
GPU Low Utilization Rules.....	219
<b>Chapter 24. Import NVTXT.....</b>	<b>221</b>
Commands.....	222
<b>Chapter 25. Visual Studio Integration.....</b>	<b>224</b>
<b>Chapter 26. Troubleshooting.....</b>	<b>226</b>
26.1. General Troubleshooting.....	226
26.2. CLI Troubleshooting.....	227
26.3. Launch Processes in Stopped State.....	227
LD_PRELOAD.....	228
Launcher.....	228
26.4. GUI Troubleshooting.....	229
Ubuntu 18.04/20.04 and CentOS 7/8 with root privileges.....	229
Ubuntu 18.04/20.04 and CentOS 7/8 without root privileges.....	230
Other platforms, or if the previous steps did not help.....	230
26.5. Symbol Resolution.....	230
Broken Backtraces on Tegra.....	232
Debug Versions of ELF Files.....	233
26.6. Logging.....	234
Verbose Logging on Linux Targets.....	234
Verbose Logging on Windows Targets.....	234

**Chapter 27. Other Resources.....236**  
 Feature Videos..... 236  
 Blog Posts..... 236  
 Training Seminars..... 236  
 Conference Presentations..... 237  
 For More Support..... 237

# Chapter 1.

## PROFILING FROM THE CLI

### 1.1. Installing the CLI on Your Target

The Nsight Systems CLI provides a simple interface to collect on a target without using the GUI. The collected data can then be copied to any system and analyzed later.

The CLI is distributed in the Target directory of the standard Nsight Systems download package. Users who want to install the CLI as a standalone tool can do so by copying the files within the Target directory. If you want the CLI output file (.qdstm) to be auto-converted (to .nsys-rep) after the analysis is complete, you will need to copy the host directory as well.

If you wish to run the CLI without root (recommended mode), you will want to install in a directory where you have full access.

Note that you must run the CLI on Windows as administrator.

### 1.2. Command Line Options

The Nsight Systems command lines can have one of two forms:

```
nsys [global_option]
```

or

```
nsys [command_switch][optional command_switch_options][application] [optional application_options]
```

All command line options are case sensitive. For command switch options, when short options are used, the parameters should follow the switch after a space; e.g. **-s process-tree**. When long options are used, the switch should be followed by an equal sign and then the parameter(s); e.g. **--sample=process-tree**.

For this version of Nsight Systems, if you launch a process from the command line to begin analysis, the launched process will be terminated when collection is complete, including runs with --duration set, unless the user specifies the --kill none option (details

below). The exception is that if the user uses NVTX, `cudaProfilerStart/Stop`, or hotkeys to control the duration, the application will continue unless `--kill` is set.

The Nsight Systems CLI supports concurrent analysis by using sessions. Each Nsight Systems session is defined by a sequence of CLI commands that define one or more collections (e.g. when and what data is collected). A session begins with either a start, launch, or profile command. A session ends with a shutdown command, when a profile command terminates, or, if requested, when all the process tree(s) launched in the session exit. Multiple sessions can run concurrently on the same system.

### 1.2.1. CLI Global Options

Short	Long	Description
-h	--help	Help message providing information about available command switches and their options.
-v	--version	Output Nsight Systems CLI version information.

### 1.3. CLI Command Switches

The Nsight Systems command line interface can be used in two modes. You may launch your application and begin analysis with options specified to the **`nsys profile`** command. Alternatively, you can control the launch of an application and data collection using interactive CLI commands.

Command	Description
profile	A fully formed profiling description requiring and accepting no further input. The command switch options used (see below table) determine when the collection starts, stops, what collectors are used (e.g. API trace, IP sampling, etc.), what processes are monitored, etc.
start	Start a collection in interactive mode. The start command can be executed before or after a launch command.
stop	Stop a collection that was started in interactive mode. When executed, all active collections stop, the CLI process terminates but the application continues running.
cancel	Cancels an existing collection started in interactive mode. All data already

Command	Description
	collected in the current collection is discarded.
launch	In interactive mode, launches an application in an environment that supports the requested options. The launch command can be executed before or after a start command.
shutdown	Disconnects the CLI process from the launched application and forces the CLI process to exit. If a collection is pending or active, it is cancelled
export	Generates an export file from an existing .nsys-rep file. For more information about the exported formats see the /documentation/nsys-exporter directory in your Nsight Systems installation directory.
stats	Post process existing Nsight Systems result, either in .nsys-rep or SQLite format, to generate statistical information.
analyze	Post process existing Nsight Systems result, either in .nsys-rep or SQLite format, to generate expert systems report.
status	Reports on the status of a CLI-based collection or the suitability of the profiling environment.
sessions	Gives information about all sessions running on the system.
nvprof	Special option to help with transition from legacy NVIDIA nvprof tool. Calling <b>nsys nvprof [options]</b> will provide the best available translation of <b>nvprof [options]</b> See <b>Migrating from NVIDIA nvprof</b> topic for details. No additional functionality of nsys will be available when using this option. Note: Not available on IBM Power targets.

### 1.3.1. CLI Profile Command Switch Options

After choosing the **profile** command switch, the following options are available.

Usage:

```
nsys [global-options] profile [options] <application> [application-arguments]
```

Short	Long	Possible Parameters	Default	Switch Description
-t	--trace	cuda, nvtx, cublas, cublas-verbose, cusparse, cusparse-verbose, cudnn, opengl, opengl-annotations, openacc, openmp, osrt, mpi, nvvideo, vulkan, vulkan-annotations, dx11, dx11-annotations, dx12, dx12-annotations, oshmem, ucx, wddm, none	cuda, opengl, nvtx, osrt	Select the API(s) to be traced. The osrt switch controls the OS runtime libraries tracing. Multiple APIs can be selected, separated by commas only (no spaces). Since OpenACC, cuDNN and cuBLAS APIs are tightly linked with CUDA, selecting one of those APIs will automatically enable CUDA tracing. Reflex SDK latency markers will be automatically collected when DX or vulkan API trace is enabled. See information on --mpi-impl option below if mpi is selected. If '<api>-annotations' is selected, the corresponding API will also be traced. If the none option is selected, no APIs are traced and no other API can be selected.

Short	Long	Possible Parameters	Default	Switch Description
				Note: cublas, cudnn, nvvideo, opengl, and vulkan are not available on IBM Power target.
	--mpi-impl	openmpi,mpich	openmpi	When using --trace=mpi to trace MPI APIs use --mpi-impl to specify which MPI implementation the application is using. If you are using a different MPI implementation, see Tracing MPI API calls section below. Calling --mpi-impl without --trace=mpi is not supported.
-s	--sample	process-tree, system-wide, none	process-tree	Select how to collect CPU IP/backtrace samples. If 'none' is selected, CPU sampling is disabled. Depending on the platform, some values may require admin or root privileges. If a target application is launched, the default is 'process-tree',

Short	Long	Possible Parameters	Default	Switch Description
				otherwise, the default is 'none'. Note: 'system-wide' is not available on all platforms. Note: If set to 'none', CPU context switch data will still be collected unless the --cpuctxsw switch is set to 'none'.
-b	--backtrace	fp,lbr,dwarf,none	lbr	Select the backtrace method to use while sampling. The option 'lbr' uses Intel(c) Corporation's Last Branch Record registers, available only with Intel(c) CPUs codenamed Haswell and later. The option 'fp' is frame pointer and assumes that frame pointers were enabled during compilation. The option 'dwarf' uses DWARF's CFI (Call Frame Information). Setting the value to 'none' can reduce

Short	Long	Possible Parameters	Default	Switch Description
				collection overhead.
	--sampling-period			<p>The number of CPU Instructions Retired events counted before a CPU instruction pointer (IP) sample is collected. If configured, backtraces may also be collected. The smaller the sampling period, the higher the sampling rate. Note that smaller sampling periods will increase overhead and significantly increase the size of the result file(s). This option is available only on some Linux targets.</p>
	--samples-per-backtrace		1	<p>The number of CPU IP samples collected for every CPU IP/backtrace sample collected. For example, if set to 4, on the fourth CPU</p>

Short	Long	Possible Parameters	Default	Switch Description
				<p>IP sample collected, a backtrace will also be collected. Lower values increase the amount of data collected. Higher values can reduce collection overhead and reduce the number of CPU IP samples dropped. If DWARF backtraces are collected, the default is 4, otherwise the default is 1. This option is available only on some Linux targets.</p>
	--sampling-frequency	integers between 100 and 8000	1000	<p>Specify the sampling/backtracing frequency. The minimum supported frequency is 100 Hz. The maximum supported frequency is 8000 Hz. This option is supported only on QNX, Linux for Tegra, and Windows targets.</p>

Short	Long	Possible Parameters	Default	Switch Description
	--sampling-trigger	timer, sched, perf, cuda	timer,sched	Specify backtrace collection trigger. Multiple APIs can be selected, separated by commas only (no spaces). Available on Nsight Systems Embedded Platforms Edition targets only.
	--cpuctxsw	process-tree, system-wide, none	process-tree	Trace OS thread scheduling activity. Select 'none' to disable tracing CPU context switches. Depending on the platform, some values may require admin or root privileges. Note: if the --sample switch is set to a value other than 'none', the --cpuctxsw setting is hardcoded to the same value as the --sample switch. If --sample=none and a target application is launched, the default is 'process-tree',

Short	Long	Possible Parameters	Default	Switch Description
				otherwise the default is 'none'.
	--command-file	< filename >	none	Open a file that contains profile switches and parse the switches. Note additional switches on the command line will override switches in the file. This flag can be specified more than once.
-y	--delay	< seconds >	0	Collection start delay in seconds.
-d	--duration	< seconds >	NA	Collection duration in seconds, duration must be greater than zero. Note that the profiler does not detach from the application, it lives until application termination.
-e	--env-var	A=B	NA	Set environment variable(s) for the application process to be launched. Environment variables should be defined as A=B. Multiple environment variables can

Short	Long	Possible Parameters	Default	Switch Description
				be specified as A=B,C=D.
	--etw-provider	"<name>,<guid>" or path to JSON file	none	Add custom ETW trace provider(s). If you want to specify more attributes than Name and GUID, provide a JSON configuration file as as outlined below. This switch can be used multiple times to add multiple providers. Note: Only available for Windows targets.
	--osrt-threshold	< nanoseconds >	1000 ns	Set the minimum time that a OS Runtime event must take before it is collected. Setting this value too low can cause high application overhead and seriously increase the size of your results file. Note: Not available for IBM Power targets.
	--osrt-backtrace-depth	integer	24	Set the depth for the backtraces

Short	Long	Possible Parameters	Default	Switch Description
				collected for OS runtime libraries calls.
	--osrt-backtrace-threshold	nanoseconds	80000	Set the duration, in nanoseconds, that all OS runtime libraries calls must execute before backtraces are collected.
	--cudabacktrace	all, none, kernel, memory, sync, other	none	When tracing CUDA APIs, enable the collection of a backtrace when a CUDA API is invoked. Significant runtime overhead may occur. Values may be combined using ','. Each value except 'none' may be appended with a threshold after ':'. Threshold is duration, in nanoseconds, that CUDA APIs must execute before backtraces are collected, e.g. 'kernel:500'. Default value for each threshold is 1000ns (1us).

Short	Long	Possible Parameters	Default	Switch Description
				Note: CPU sampling must be enabled. Note: Not available on IBM Power targets.
	--cuda-flush-interval	milliseconds	0	Set the interval, in milliseconds, when buffered CUDA data is automatically saved to storage. Immediately before data is saved to storage, a <code>cudaDeviceSynchronize</code> call is inserted into the workflow which will cause application overhead. If data is not periodically saved, <code>nsys</code> will dynamically allocate memory as needed to store data during collection. For collections over 30 seconds an interval of 10 seconds is recommended.
	--cuda-memory-usage	true, false	false	Track the GPU memory usage by CUDA kernels. Applicable only

Short	Long	Possible Parameters	Default	Switch Description
				when CUDA tracing is enabled. Note: This feature may cause significant runtime overhead.
	--cuda-um-cpu-page-faults	true, false	false	This switch tracks the page faults that occur when CPU code tries to access a memory page that resides on the device. Note that this feature may cause significant runtime overhead.
	--cuda-um-gpu-page-faults	true, false	false	This switch tracks the page faults that occur when GPU code tries to access a memory page that resides on the host. Note that this feature may cause significant runtime overhead.
-o	--output	< filename >	report#	Set report file name. Any %q{ENV_VAR} pattern in the filename will be substituted with the value of the environment variable. Any %h

Short	Long	Possible Parameters	Default	Switch Description
				pattern in the filename will be substituted with the hostname of the system. Any %p pattern in the filename will be substituted with the PID of the target process or the PID of the root process if there is a process tree. Any %% pattern in the filename will be substituted with %. Default is report#. {qdstm,nsys-rep,sqlite} in the working directory.
	--export	arrow, hdf, json, sqlite, text, none	none	Create additional output file(s) based on the data collected. WARNING: If the collection captures a large amount of data, creating the export file may take several minutes to complete.
	--stats	true, false	false	Generate summary statistics after the collection. WARNING: When set to

Short	Long	Possible Parameters	Default	Switch Description
				true, an SQLite database will be created after the collection. If the collection captures a large amount of data, creating the database file may take several minutes to complete.
-f	--force-overwrite	true, false	false	If true, overwrite all existing result files with same output filename (.qdstrm, .nsys-rep, .arrows, .hdf, .json, .sqlite, .)
-w	--show-output	true, false	true	If true, send target process' stdout and stderr streams to the console.
-n	--inherit-environment	true, false	true	When true, the current environment variables and the tool's environment variables will be specified for the launched process. When false, only the tool's environment variables will be specified for the launched process.
-x	--stop-on-exit	true, false	true	If true, stop collecting automatically

Short	Long	Possible Parameters	Default	Switch Description
				when the launched process has exited or when the duration expires - whichever occurs first. If false, duration must be set and the collection stops only when the duration expires. Nsight Systems does not officially support runs longer than 5 minutes.
	--wait	primary,all	all	If primary, the CLI will wait on the application process termination. If all, the CLI will additionally wait on re-parented processes created by the application.
	--trace-fork-before-exec	true, false	false	If true, trace any child process after fork and before they call one of the exec functions. Beware, tracing in this interval relies on undefined behavior and might

Short	Long	Possible Parameters	Default	Switch Description
				cause your application to crash or deadlock. Note: Not available for Windows targets.
-c	--capture-range	none, cudaProfilerApi, hotkey, nvtx	none	When --capture-range is used, profiling will start only when appropriate start API or hotkey is invoked. If --capture-range is set to none, start/stop API calls and hotkeys will be ignored. Note: Hotkey works for graphic applications only.
	--capture-range-end	none, stop, stop-shutdown, repeat[:N], repeat-shutdown:N	stop-shutdown	Specify the desired behavior when a capture range ends. Applicable only when used along with --capture-range option. If <b>none</b> , capture range end will be ignored. If <b>stop</b> , collection will stop at capture range end. Any subsequent capture ranges

Short	Long	Possible Parameters	Default	Switch Description
				<p>will be ignored. Target app will continue running.</p> <p>If <b>stop-shutdown</b>, collection will stop at capture range end and session will be shutdown. If <b>repeat[:N]</b>, collection will stop at capture range end and subsequent capture ranges will trigger more collections. Use the optional <b>:N</b> to specify max number of capture ranges to be honored. Any subsequent capture ranges will be ignored once N capture ranges are collected.</p> <p>If <b>repeat-shutdown:N</b>, same behavior as <b>repeat:N</b> but session will be shutdown after N ranges.</p> <p>For <b>stop-shutdown</b> and <b>repeat-shutdown:N</b>, as always, use --kill option to specify whether target</p>

Short	Long	Possible Parameters	Default	Switch Description
				app should be terminated when shutting down session.
-p	--nvtx-capture	range@domain,range,range@		Specify NVTX capture range. See below for details. This option is applicable only when used along with --capture-range=nvtx.
	--nvtx-domain-include	default, <domain_names>		Choose to only include NVTX events from a comma separated list of domains. 'default' filters the NVTX default domain. A domain with this name or commas in a domain name must be escaped with '\'. Note: Only one of --nvtx-domain-include and --nvtx-domain-exclude can be used. This option is only applicable when --trace=nvtx is specified.
	--nvtx-domain-exclude	default, <domain_names>		Choose to exclude NVTX events from a comma separated list

Short	Long	Possible Parameters	Default	Switch Description
				of domains. 'default' excludes NVTX events without a domain. A domain with this name or commas in a domain name must be escaped with '\'. Note: Only one of --nvtx-domain-include and --nvtx-domain-exclude can be used. This option is only applicable when --trace=nvtx is specified.
	--ftrace			Collect ftrace events. Argument should list events to collect as: subsystem1/event1,subsystem2/event2. Requires root. No ftrace events are collected by default. Note: Not available on IBM Power targets.
	--ftrace-keep-user-config			Skip initial ftrace setup and collect already configured events. Default resets the ftrace configuration.

Short	Long	Possible Parameters	Default	Switch Description
	<code>--vsync</code>	true, false	false	Collect vsync events. If collection of vsync events is enabled, display/display_scanline/fttrace events will also be captured.
	<code>--dx-force-declare-adapter-removal-support</code>	true, false	false	The Nsight Systems trace initialization involves creating a D3D device and discarding it. Enabling this flag makes a call to <code>DXGIDeclareAdapterRemovalSupport</code> before device creation. Requires DX11 or DX12 trace to be enabled.
	<code>--gpuctxsw</code>	true,false	false	Trace GPU context switches. Note that this requires driver r435.17 or later and root permission. Not available on IBM Power targets.
	<code>--gpu-metrics-device</code>	GPU ID, help, none	none	Collect GPU Metrics from specified devices. Determine GPU IDs by using <code>--gpu-metrics-</code>

Short	Long	Possible Parameters	Default	Switch Description
				<b>device=help</b> switch.
	--gpu-metrics-frequency	integer	10000	Specify GPU Metrics sampling frequency. Minimum supported frequency is 10 (Hz). Maximum supported frequency is 200000(Hz).
	--gpu-metrics-set	index	first	Specify metric set for GPU Metrics sampling. The argument must be one of indices reported by <b>--gpu-metrics-set=help</b> switch. Default is the first metric set that supports selected GPU.
	--nic-metrics	true, false	false	(Experimental) Collect metrics from supported NIC/HCA devices
	--kill	none, sigkill, sigterm, signal number	sigterm	Send signal to the target application's process group. Can be used with --duration or range markers.
	--session-new	[a-Z][0-9,a-Z,spaces]	profile-<id>-<application>	Name the session created by the

Short	Long	Possible Parameters	Default	Switch Description
				command. Name must start with an alphabetical character followed by printable or space characters. Any <b>%q{ENV_VAR}</b> pattern will be substituted with the value of the environment variable. Any <b>%h</b> pattern will be substituted with the hostname of the system. Any <b>%</b> pattern will be substituted with <b>%</b> .
	--retain-etw-files	true, false	false	If true, retains ETW files generated by the trace, merges and moves the files to the output directory.
	--opengl-gpu-workload	true, false	true	If true, trace the OpenGL workloads' GPU activity. Note that this switch is applicable only when --trace=opengl is specified. This option is not supported

Short	Long	Possible Parameters	Default	Switch Description
				on IBM Power targets.
	--vulkan-gpu-workload	true, false	true	If true, trace the Vulkan workloads' GPU activity. Note that this switch is applicable only when --trace=vulkan is specified. This option is not supported on QNX.
	--dx12-gpu-workload	true, false	true	If true, trace the DX12 workloads' GPU activity. Note that this switch is applicable only when --trace=dx12 is specified. This option is only supported on Windows targets.
	--dx12-wait-calls	true, false	true	If true, trace wait calls that block on fences for DX12. Note that this switch is applicable only when --trace=dx12 is specified. This option is only supported on Windows targets.

Short	Long	Possible Parameters	Default	Switch Description
	--wddm-additional-events	true, false	true	If true, collect additional range of ETW events, including context status, allocations, sync wait and signal events, etc. Note that this switch is applicable only when --trace=wddm is specified. This option is only supported on Windows targets.
	--hotkey-capture	'F1' to 'F12'	'F12'	Hotkey to trigger the profiling session. Note that this switch is applicable only when --capture-range=hotkey is specified.
	--cpu-core-events	0x11,0x13,...,none	%s	Collect per-core PMU counters. Multiple values can be selected, separated by commas only (no spaces). Use the --cpu-core-events=help switch to see the full list of values. Available in Nsight Systems Embedded

Short	Long	Possible Parameters	Default	Switch Description
				Platforms Edition only.
	--cpu-cluster-events	0x16, 0x17, ..., none	none	Collect per-cluster Uncore PMU counters. Multiple values can be selected, separated by commas only (no spaces). Use the --cpu-cluster-events=help switch to see the full list of values. Available in Nsight Systems Embedded Platforms Edition only.
	--cpu-socket-events	0x2a, 0x2c, ..., none	none	Collect per-socket Uncore PMU counters. Multiple values can be selected, separated by commas only (no spaces). Use the --cpu-cluster-events=help switch to see the full list of values. Available in Nsight Systems Embedded Platforms Edition only.
	--process-scope	main, process-tree, system-wide	main	Select which process(es) to trace. Available in Nsight Systems

Short	Long	Possible Parameters	Default	Switch Description
				Embedded Platforms Edition only. Nsight Systems Workstation Edition will always trace system-wide in this version of the tool.
	--accelerator-trace	none, nvmedia	none	Collect other accelerators workload trace from the hardware engine units. Available in Nsight Systems Embedded Platforms Edition only.
	--clock-frequency-changes	true, false	false	Collect clock frequency changes. Available in Nsight Systems Embedded Platforms Edition only.
	--xhv-trace	< filepath pct.json >	none	Collect hypervisor trace. Available in Nsight Systems Embedded Platforms Edition only.
	--el1-sampling	true, false	false	Enable EL1 sampling. Available in Nsight Systems Embedded Platforms Edition only.

Short	Long	Possible Parameters	Default	Switch Description
	<code>--el1-sampling-config</code>	< filepath config.json >	none	EL1 sampling config. Available in Nsight Systems Embedded Platforms Edition only.
	<code>--run-as</code>	< username >	none	Run the target application as the specified username. If not specified, the target application will be run by the same user as Nsight Systems. Requires root privileges. Available for Linux targets only.

### 1.3.2. CLI Start Command Switch Options

After choosing the **start** command switch, the following options are available. Usage:

```
nsys [global-options] start [options]
```

Short	Long	Possible Parameters	Default	Switch Description
<code>-c</code>	<code>--capture-range</code>	none, cudaProfilerApi, hotkey, nvtx	none	When <code>--capture-range</code> is used, profiling will start only when appropriate start API or hotkey is invoked. If <code>--capture-range</code> is set to none, start/stop API calls and hotkeys will be ignored. Note:

Short	Long	Possible Parameters	Default	Switch Description
				hotkey works for graphic applications only.
-o	--output	< filename >	report#	Set report file name. Any %q{ENV_VAR} pattern in the filename will be substituted with the value of the environment variable. Any %h pattern in the filename will be substituted with the hostname of the system. Any %p pattern in the filename will be substituted with the PID of the target process or the PID of the root process if there is a process tree. Any %% pattern in the filename will be substituted with %. Default is report#. {qdstm,nsys-rep,sqlite} in the working directory.
	--export	arrow, hdf, json, sqlite, text, none	none	Create additional output file(s) based on the data collected.

Short	Long	Possible Parameters	Default	Switch Description
				WARNING: If the collection captures a large amount of data, creating the export file may take several minutes to complete.
	--stats	true, false	false	Generate summary statistics after the collection. WARNING: When set to true, an SQLite database will be created after the collection. If the collection captures a large amount of data, creating the database file may take several minutes to complete.
-f	--force-overwrite	true, false	false	If true, overwrite all existing result files with same output filename (.qdstrm, .nsys-rep, .arrows, .hdf, .json, .sqlite, .
-x	--stop-on-exit	true, false	true	If true, stop collecting automatically when all tracked processes have exited or when <b>stop</b> command is issued - whichever occurs first.

Short	Long	Possible Parameters	Default	Switch Description
				If false, stop only on <b>stop</b> command. Note: When this is true, <b>stop</b> command is optional. Nsight Systems does not officially support runs longer than 5 minutes.
	--capture-range-end	none, stop, stop-shutdown, repeat[:N], repeat-shutdown:N	stop-shutdown	Specify the desired behavior when a capture range ends. Applicable only when used along with --capture-range option. If <b>none</b> , capture range end will be ignored. If <b>stop</b> , collection will stop at capture range end. Any subsequent capture ranges will be ignored. Target app will continue running. If <b>stop-shutdown</b> , collection will stop at capture range end and session will be shutdown. If <b>repeat[:N]</b> , collection will stop at capture range end and

Short	Long	Possible Parameters	Default	Switch Description
				<p>subsequent capture ranges will trigger more collections. Use the optional <b>:N</b> to specify max number of capture ranges to be honored. Any subsequent capture ranges will be ignored once N capture ranges are collected.</p> <p>If <b>repeat-shutdown:N</b>, same behavior as <b>repeat:N</b> but session will be shutdown after N ranges. For <b>stop-shutdown</b> and <b>repeat-shutdown:N</b>, as always use --kill option to specify whether target app should be terminated when shutting down session.</p>
	--etw-provider	"<name>,<guid>" or path to JSON file	none	Add custom ETW trace provider(s). If you want to specify more attributes than Name and GUID, provide a JSON configuration file as as

Short	Long	Possible Parameters	Default	Switch Description
				outlined below. This switch can be used multiple times to add multiple providers. Note: Only available for Windows targets.
	--dx-force-declare-adapter-removal-support	true, false	false	The Nsight Systems trace initialization involves creating a D3D device and discarding it. Enabling this flag makes a call to <code>DXGIDeclareAdapterRemovalSupport</code> before device creation. Requires DX11 or DX12 trace to be enabled.
	--ftrace			Collect ftrace events. Argument should list events to collect as: subsystem1/event1, subsystem2/event2. Requires root. No ftrace events are collected by default. Note: Not supported on IBM Power targets.
	--ftrace-keep-user-config			Skip initial ftrace setup and collect already configured

Short	Long	Possible Parameters	Default	Switch Description
				events. Default resets the ftrace configuration.
	<code>--gpu-metrics-device</code>	GPU ID, help, none	none	Collect GPU Metrics from specified devices. Determine GPU IDs by using <code>--gpu-metrics-device=help</code> switch.
	<code>--gpu-metrics-frequency</code>	integer	10000	Specify GPU Metrics sampling frequency. Minimum supported frequency is 10 (Hz). Maximum supported frequency is 200000(Hz).
	<code>--gpu-metrics-set</code>	index	first	Specify metric set for GPU Metrics sampling. The argument must be one of indices reported by <code>--gpu-metrics-set=help</code> switch. Default is the first metric set that supports selected GPU.
	<code>--nic-metrics</code>	true, false	false	(Experimental) Collect metrics from supported NIC/HCA devices

Short	Long	Possible Parameters	Default	Switch Description
	--gpuctxsw	true,false	false	Trace GPU context switches. Note that this requires driver r435.17 or later and root permission. Not supported on IBM Power targets.
-s	--sample	process-tree, system-wide, none	process-tree	Select how to collect CPU IP/backtrace samples. If 'none' is selected, CPU sampling is disabled. Depending on the platform, some values may require admin or root privileges. If a target application is launched, the default is 'process-tree', otherwise, the default is 'none'. Note: 'system-wide' is not available on all platforms. Note: If set to 'none', CPU context switch data will still be collected unless the --cpuctxsw switch is set to 'none'.

Short	Long	Possible Parameters	Default	Switch Description
-b	--backtrace	fp,lbr,dwarf,none	lbr	Select the backtrace method to use while sampling. The option 'lbr' uses Intel(c) Corporation's Last Branch Record registers, available only with Intel(c) CPUs codenamed Haswell and later. The option 'fp' is frame pointer and assumes that frame pointers were enabled during compilation. The option 'dwarf' uses DWARF's CFI (Call Frame Information). Setting the value to 'none' can reduce collection overhead.
	--sampling-period			The number of CPU Instructions Retired events counted before a CPU instruction pointer (IP) sample is collected. If configured, backtraces

Short	Long	Possible Parameters	Default	Switch Description
				may also be collected. The smaller the sampling period, the higher the sampling rate. Note that smaller sampling periods will increase overhead and significantly increase the size of the result file(s). This option is available only on some Linux targets.
	--samples-per-backtrace		1	The number of CPU IP samples collected for every CPU IP/backtrace sample collected. For example, if set to 4, on the fourth CPU IP sample collected, a backtrace will also be collected. Lower values increase the amount of data collected. Higher values can reduce collection overhead and reduce the number of CPU

Short	Long	Possible Parameters	Default	Switch Description
				IP samples dropped. If DWARF backtraces are collected, the default is 4, otherwise the default is 1. This option is available only on some Linux targets.
	--sampling-frequency	integers between 100 and 8000	1000	Specify the sampling/backtracing frequency. The minimum supported frequency is 100 Hz. The maximum supported frequency is 8000 Hz. This option is supported only on QNX, Linux for Tegra, and Windows targets.
	--sampling-trigger	timer, sched, perf, cuda	timer,sched	Specify backtrace collection trigger. Multiple APIs can be selected, separated by commas only (no spaces). Available on Nsight Systems Embedded Platforms Edition targets only.

Short	Long	Possible Parameters	Default	Switch Description
	--cpuctxsw	process-tree, system-wide, none	process-tree	Trace OS thread scheduling activity. Select 'none' to disable tracing CPU context switches. Depending on the platform, some values may require admin or root privileges. Note: if the --sample switch is set to a value other than 'none', the --cpuctxsw setting is hardcoded to the same value as the --sample switch. If --sample=none and a target application is launched, the default is 'process-tree', otherwise the default is 'none'.
	--session	session identifier	none	Start the application in the indicated session. The option argument must represent a valid session name or ID as reported by <b>nsys sessions list</b> . Any

Short	Long	Possible Parameters	Default	Switch Description
				<code>%q{ENV_VAR}</code> pattern will be substituted with the value of the environment variable. Any <code>%h</code> pattern will be substituted with the hostname of the system. Any <code>%</code> pattern will be substituted with <code>%</code> .
	<code>--session-new</code>	<code>[a-Z][0-9,a-Z,spaces]</code>	<code>[default]</code>	Start the application in a new session. Name must start with an alphabetical character followed by printable or space characters. Any <code>%q{ENV_VAR}</code> pattern will be substituted with the value of the environment variable. Any <code>%h</code> pattern will be substituted with the hostname of the system. Any <code>%</code> pattern will be substituted with <code>%</code> .
	<code>--vsync</code>	<code>true, false</code>	<code>false</code>	Collect vsync events. If collection of vsync events

Short	Long	Possible Parameters	Default	Switch Description
				is enabled, display/display_scanline ftrace events will also be captured.
	--process-scope	main, process-tree, system-wide	main	Select which process(es) to trace. Available in Nsight Systems Embedded Platforms Edition only. Nsight Systems Workstation Edition will always trace system-wide in this version of the tool.
	--accelerator-trace	none, nvmedia	none	Collect other accelerators workload trace from the hardware engine units. Available in Nsight Systems Embedded Platforms Edition only.
	--clock-frequency-changes	true, false	false	Collect clock frequency changes. Available in Nsight Systems Embedded Platforms Edition only.
	--xhv-trace	< filepath pct.json >	none	Collect hypervisor trace. Available in Nsight

Short	Long	Possible Parameters	Default	Switch Description
				Systems Embedded Platforms Edition only.
	--el1-sampling	true, false	false	Enable EL1 sampling. Available in Nsight Systems Embedded Platforms Edition only.
	--el1-sampling-config	< filepath config.json >	none	EL1 sampling config. Available in Nsight Systems Embedded Platforms Edition only.

### 1.3.3. CLI Stop Command Switch Options

After choosing the **stop** command switch, the following options are available. Usage:

```
nsys [global-options] stop [options]
```

Short	Long	Possible Parameters	Default	Switch Description
	--session	session identifier	none	Stop the indicated session. The option argument must represent a valid session name or ID as reported by <b>nsys sessions list</b> . Any <b>%q{ENV_VAR}</b> pattern will be substituted with the value of the environment variable. Any

Short	Long	Possible Parameters	Default	Switch Description
				<b>%h</b> pattern will be substituted with the hostname of the system. Any <b>%</b> pattern will be substituted with <b>%</b> .

### 1.3.4. CLI Cancel Command Switch Options

After choosing the **cancel** command switch, the following options are available. Usage:

```
nsys [global-options] cancel [options]
```

Short	Long	Possible Parameters	Default	Switch Description
	--session	session identifier	none	Cancel the indicated session. The option argument must represent a valid session name or ID as reported by <b>nsyssessions list</b> . Any <b>%q{ENV_VAR}</b> pattern will be substituted with the value of the environment variable. Any <b>%h</b> pattern will be substituted with the hostname of the system. Any <b>%</b> pattern will be substituted with <b>%</b> .

### 1.3.5. CLI Launch Command Switch Options

After choosing the **launch** command switch, the following options are available. Usage:

```
nsys [global-options] launch [options] <application> [application-arguments]
```

Short	Long	Possible Parameters	Default	Switch Description
-t	--trace	cuda, nvtx, cublas, cublas-verbose, cusparse, cusparse-verbose, cudnn, opengl, opengl-annotations, openacc, openmp, osrt, mpi, nvvideo, vulkan, vulkan-annotations, dx11, dx11-annotations, dx12, dx12-annotations, oshmem, ucx, wddm, none	cuda, opengl, nvtx, osrt	Select the API(s) to be traced. The osrt switch controls the OS runtime libraries tracing. Multiple APIs can be selected, separated by commas only (no spaces). Since OpenACC, cuDNN and cuBLAS APIs are tightly linked with CUDA, selecting one of those APIs will automatically enable CUDA tracing. Reflex SDK latency markers will be automatically collected when DX or vulkan API trace is enabled. See information on --mpi-impl option below if mpi is selected. If '<api>-annotations' is selected, the corresponding API will also be traced. If the

Short	Long	Possible Parameters	Default	Switch Description
				none option is selected, no APIs are traced and no other API can be selected. Note: cublas, cudnn, nvvideo, opengl, and vulkan are not available on IBM Power target.
	--mpi-impl	openmpi,mpich	openmpi	When using --trace=mpi to trace MPI APIs use --mpi-impl to specify which MPI implementation the application is using. If you are using a different MPI implementation, see Tracing MPI API calls section below. Calling --mpi-impl without --trace=mpi is not supported.
	--command-file	< filename >	none	Open a file that contains launch switches and parse the switches. Note additional switches on the command line will override switches in the file. This flag can be specified more than once.

Short	Long	Possible Parameters	Default	Switch Description
-e	--env-var	A=B	NA	Set environment variable(s) for the application process to be launched. Environment variables should be defined as A=B. Multiple environment variables can be specified as A=B,C=D.
	--etw-provider	"<name>,<guid>" or path to JSON file	none	Add custom ETW trace provider(s). If you want to specify more attributes than Name and GUID, provide a JSON configuration file as outlined below. This switch can be used multiple times to add multiple providers. Note: Only available for Windows targets.
	--osrt-threshold	< nanoseconds >	1000 ns	Set the minimum time that a OS Runtime event must take before it is collected. Setting this value too low

Short	Long	Possible Parameters	Default	Switch Description
				can cause high application overhead and seriously increase the size of your results file. Note: Not available for IBM Power targets.
	--osrt-backtrace-depth	integer	24	Set the depth for the backtraces collected for OS runtime libraries calls.
	--osrt-backtrace-threshold	nanoseconds	80000	Set the duration, in nanoseconds, that all OS runtime libraries calls must execute before backtraces are collected.
	--cudabacktrace	all, none, kernel, memory, sync, other	none	When tracing CUDA APIs, enable the collection of a backtrace when a CUDA API is invoked. Significant runtime overhead may occur. Values may be combined using ','. Each value except 'none' may be appended with a threshold after ':'. 

Short	Long	Possible Parameters	Default	Switch Description
				Threshold is duration, in nanoseconds, that CUDA APIs must execute before backtraces are collected, e.g. 'kernel:500'. Default value for each threshold is 1000ns (1us). Note: CPU sampling must be enabled. Note: Not available on IBM Power targets.
	--cuda-flush-interval	milliseconds	0	Set the interval, in milliseconds, when buffered CUDA data is automatically saved to storage. Immediately before data is saved to storage, a <code>cudaDeviceSynchronize</code> call is inserted into the workflow which will cause application overhead. If data is not periodically saved, nsys will dynamically allocate memory as needed to store

Short	Long	Possible Parameters	Default	Switch Description
				data during collection. For collections over 30 seconds an interval of 10 seconds is recommended.
	--cuda-memory-usage	true, false	false	Track the GPU memory usage by CUDA kernels. Applicable only when CUDA tracing is enabled. Note: This feature may cause significant runtime overhead.
	--cuda-um-cpu-page-faults	true, false	false	This switch tracks the page faults that occur when CPU code tries to access a memory page that resides on the device. Note that this feature may cause significant runtime overhead.
	--cuda-um-gpu-page-faults	true, false	false	This switch tracks the page faults that occur when GPU code tries to access a memory page that resides on the host. Note that this feature may cause significant

Short	Long	Possible Parameters	Default	Switch Description
				runtime overhead.
-w	--show-output	true, false	true	If true, send target process' stdout and stderr streams to the console
-n	--inherit-environment	true, false	true	When true, the current environment variables and the tool's environment variables will be specified for the launched process. When false, only the tool's environment variables will be specified for the launched process.
-p	--nvtx-capture	message@idomain	none	Specify NVTX capture range. See below for details.
	--nvtx-domain-include	default, <domain_names>		Choose to only include NVTX events from a comma separated list of domains. 'default' filters the NVTX default domain. A domain with this name or commas in a domain name must be escaped with '\'. Note: Only

Short	Long	Possible Parameters	Default	Switch Description
				one of --nvtx-domain-include and --nvtx-domain-exclude can be used. This option is only applicable when --trace=nvtx is specified.
	--nvtx-domain-exclude	default, <domain_names>		Choose to exclude NVTX events from a comma separated list of domains. 'default' excludes NVTX events without a domain. A domain with this name or commas in a domain name must be escaped with '\'. Note: Only one of --nvtx-domain-include and --nvtx-domain-exclude can be used. This option is only applicable when --trace=nvtx is specified.
	--trace-fork-before-exec	true, false	false	If true, trace any child process after fork and before they call one of the exec functions. Beware, tracing

Short	Long	Possible Parameters	Default	Switch Description
				in this interval relies on undefined behavior and might cause your application to crash or deadlock. Note: Not available for Windows targets.
	--wait	primary,all	all	If primary, the CLI will wait on the application process termination. If all, the CLI will additionally wait on re-parented processes created by the application.
	--session	session identifier	none	Launch the application in the indicated session. The option argument must represent a valid session name or ID as reported by <b>nsys sessions list</b> . Any <b>%q{ENV_VAR}</b> pattern will be substituted with the value of the environment variable. Any <b>%h</b> pattern will

Short	Long	Possible Parameters	Default	Switch Description
				be substituted with the hostname of the system. Any % % pattern will be substituted with %.
	--session-new	[a-Z][0-9,a-Z,spaces]	[default]	Launch the application in a new session. Name must start with an alphabetical character followed by printable or space characters. Any %q{ENV_VAR} pattern will be substituted with the value of the environment variable. Any %h pattern will be substituted with the hostname of the system. Any % % pattern will be substituted with %.
	--opengl-gpu-workload	true, false	true	If true, trace the OpenGL workloads' GPU activity. Note that this switch is applicable only when --trace=opengl is specified. This option is not supported

Short	Long	Possible Parameters	Default	Switch Description
				on IBM Power targets.
	--vulkan-gpu-workload	true, false	true	If true, trace the Vulkan workloads' GPU activity. Note that this switch is applicable only when --trace=vulkan is specified. This option is not supported on QNX.
	--dx12-gpu-workload	true, false	true	If true, trace the DX12 workloads' GPU activity. Note that this switch is applicable only when --trace=dx12 is specified. This option is only supported on Windows targets.
	--dx12-wait-calls	true, false	true	If true, trace wait calls that block on fences for DX12. Note that this switch is applicable only when --trace=dx12 is specified. This option is only supported on Windows targets.

Short	Long	Possible Parameters	Default	Switch Description
	--wddm-additional-events	true, false	true	If true, collect additional range of ETW events, including context status, allocations, sync wait and signal events, etc. Note that this switch is applicable only when --trace=wddm is specified. This option is only supported on Windows targets.
	--hotkey-capture	'F1' to 'F12'	'F12'	Hotkey to trigger the profiling session. Note that this switch is applicable only when --capture-range=hotkey is specified.
	--cpu-core-events	0x11,0x13,...,none	%s	Collect per-core PMU counters. Multiple values can be selected, separated by commas only (no spaces). Use the --cpu-core-events=help switch to see the full list of values. Available in Nsight Systems Embedded

Short	Long	Possible Parameters	Default	Switch Description
				Platforms Edition only.
	--cpu-cluster-events	0x16, 0x17, ..., none	none	Collect per-cluster Uncore PMU counters. Multiple values can be selected, separated by commas only (no spaces). Use the --cpu-cluster-events=help switch to see the full list of values. Available in Nsight Systems Embedded Platforms Edition only.
	--cpu-socket-events	0x2a, 0x2c, ..., none	none	Collect per-socket Uncore PMU counters. Multiple values can be selected, separated by commas only (no spaces). Use the --cpu-cluster-events=help switch to see the full list of values. Available in Nsight Systems Embedded Platforms Edition only.
	--run-as	< username >	none	Run the target application as the specified username. If not specified,

Short	Long	Possible Parameters	Default	Switch Description
				the target application will be run by the same user as Nsight Systems. Requires root privileges. Available for Linux targets only.

### 1.3.6. CLI Shutdown Command Switch Options

After choosing the **shutdown** command switch, the following options are available.

Usage:

```
nsys [global-options] shutdown [options]
```

Short	Long	Possible Parameters	Default	Switch Description
	--kill	none, sigkill, sigterm, signal number	sigterm	Send signal to the target application's process group.
	--session	session identifier	none	Shutdown the indicated session. The option argument must represent a valid session name or ID as reported by <b>nsys sessions list</b> . Any <b>%q{ENV_VAR}</b> pattern will be substituted with the value of the environment variable. Any <b>%h</b> pattern will be substituted with the

Short	Long	Possible Parameters	Default	Switch Description
				hostname of the system. Any % pattern will be substituted with %.

### 1.3.7. CLI Export Command Switch Options

After choosing the **export** command switch, the following options are available. Usage:

```
nsys [global-options] export [options] [nsys-rep-file]
```

Short	Long	Possible Parameters	Default	Switch Description
-o	--output	<filename>	<inputfile.ext>	Set the .output filename. The default is the .nsys-rep filename with the extension for the chosen format.
-t	--type	arrow, hdf, info, json, sqlite, text	sqlite	Export format type. HDF format is supported only on x86_64 Linux and Windows
-f	--force-overwrite	true, false	false	If true, overwrite existing result file
-l	--lazy	true, false	true	Controls if table creation is lazy or not. When true, a table will only be created when it contains data. This option will be deprecated in the future, and all exports will be non-

Short	Long	Possible Parameters	Default	Switch Description
				lazy. This affects SQLite and HDF5 exports only.
-q	--quiet	true, false	false	If true, do not display progress bar
	--separate-strings	true,false	false	Output stored strings and thread names separately, with one value per line. This affects JSON and text output only.

### 1.3.8. CLI Stats Command Switch Options

The **nsys stats** command generates a series of summary or trace reports. These reports can be output to the console, or to individual files, or piped to external processes. Reports can be rendered in a variety of different output formats, from human readable columns of text, to formats more appropriate for data exchange, such as CSV.

Reports are generated from an SQLite export of a .nsys-rep file. If a .nsys-rep file is specified, Nsight Systems will look for an accompanying SQLite file and use it. If no SQLite file exists, one will be exported and created.

Individual reports are generated by calling out to scripts that read data from the SQLite file and return their report data in CSV format. Nsight Systems ingests this data and formats it as requested, then displays the data to the console, writes it to a file, or pipes it to an external process. Adding new reports is as simple as writing a script that can read the SQLite file and generate the required CSV output. See the shipped scripts as an example. Both reports and formatters may take arguments to tweak their processing. For details on shipped scripts and formatters, see **Report Scripts** topic.

Reports are processed using a three-tuple that consists of 1) the requested report (and any arguments), 2) the presentation format (and any arguments), and 3) the output (filename, console, or external process). The first report specified uses the first format specified, and is presented via the first output specified. The second report uses the second format for the second output, and so forth. If more reports are specified than formats or outputs, the format and/or output list is expanded to match the number of provided reports by repeating the last specified element of the list (or the default, if nothing was specified).

**nsys stats** is a very powerful command and can handle complex argument structures, please see the topic below on Example Stats Command Sequences.

After choosing the **stats** command switch, the following options are available. Usage:

**nsys** [global-options] **stats** [options] [input-file]

Short	Long	Possible Parameters	Default	Switch Description
	--help-reports	<report_name>, ALL, [none]	none	With no argument, give a summary of the available summary and trace reports. If a report name is given, a more detailed explanation of the report is displayed. If <b>ALL</b> is given, a more detailed explanation of all available reports is displayed.
	--help-formats	<format_name>, ALL, [none]	none	With no argument, give a summary of the available output formats. If a format name is given, a more detailed explanation of that format is displayed. If <b>ALL</b> is given, a more detailed explanation of all available formats is displayed.
	--sqlite	<file.sqlite>		Specify the SQLite export filename. If this file exists, it will be used. If this file doesn't exist (or if --force-

Short	Long	Possible Parameters	Default	Switch Description
				export was given) this file will be created from the specified .nsys-rep file before report processing. This option cannot be used if the specified input file is also an SQLite file.
-r	--report	See <b>Report Scripts</b>		Specify the report(s) to generate, including any arguments. This option may be used multiple times. Multiple reports may also be specified using a comma-separated list (<name[:args...] [name[:args...]]...>). If no reports are specified, the following will be used as the default report set: cudaapisum, gpukernsum, gpumemtimesum, gpumemsum, gpumemsize, osrtsum, nvtxppsum, openmpevtsum. See <b>Report Scripts</b> section for details about existing built-in scripts

Short	Long	Possible Parameters	Default	Switch Description
				and how to make your own.
-f	--format	column, table, csv, tsv, json, hdoc, htable, .		Specify the output format of the corresponding report(s). The special name "." indicates the default format for the given output. The default format for console is column, while files and process outputs default to csv. This option may be used multiple times. Multiple formats may also be specified using a comma-separated list (<name[:args...] [name[:args...]]...>). See <b>Report Scripts</b> for options available with each format.
-o	--output	-, @<command>, <basename>, .	-	Specify the output mechanism for the corresponding reports(s). There are three output mechanisms: print to console (-), output

Short	Long	Possible Parameters	Default	Switch Description
				to command (@<command>), or output to file (<basename>). The option "." can be used to specify using the default basefile, which is the basename of the input file. The filename used will be <basename>_<report&args>.<ou
	--report-dir			Add a directory to the path used to find report scripts. This is usually only needed if you have one or more directories with personal scripts. This option may be used multiple times. Each use adds a new directory to the end of the path. The last two entries in the path will always be the current working directory, followed by the directory containing the shipped <b>nsys</b> reports.
	--force-export	true, false	false	Force a re-export of the SQLite file from the

Short	Long	Possible Parameters	Default	Switch Description
				specified .nsys-rep file, even if an SQLite file already exists.
	--force-overwrite	true, false	false	Overwrite any existing report file(s).
-q	--quiet			Only display errors.

### 1.3.9. CLI Analyze Command Switch Options

The **nsys analyze** command generates and outputs to the terminal a report using expert system rules on existing results. Reports are generated from an SQLite export of a .nsys-rep file. If a .nsys-rep file is specified, Nsight Systems will look for an accompanying SQLite file and use it. If no SQLite export file exists, one will be created.

After choosing the **analyze** command switch, the following options are available.  
Usage:

**nsys [global-options] analyze [options] [input-file]**

Short	Long	Possible Parameters	Default	Switch Description
-h	--help			Print help message.
	--help-rules	<report_name>, ALL, [none]	none	With no argument, list available rules with a short description. If a rule name is given, a more detailed explanation of the rule is displayed. If <b>ALL</b> is given, a more detailed explanation of all available rules is displayed.
	--sqlite	<file.sqlite>		Specify the SQLite export

Short	Long	Possible Parameters	Default	Switch Description
				filename. If this file exists, it will be used. If this file doesn't exist (or if --force-export was given) this file will be created from the specified .nsys-rep file before report processing. This option cannot be used if the specified input file is also an SQLite file.
-r	--rule	asyn-memcpy-pageable, sync-memcpy, sync-memset, sync-api, gpu-starvation, gpu-low-utilization	all	Specify the rules(s) to execute, including any arguments. This option may be used multiple times. Multiple reports may also be specified using a comma-separated list. See <b>Expert Systems</b> section for details on all rules.
	--force-export	true, false	false	Force a re-export of the SQLite file from the specified .nsys-rep file, even if an SQLite file already exists.

Short	Long	Possible Parameters	Default	Switch Description
-q	--quiet			Do not display verbose messages.

### 1.3.10. CLI Status Command Switch Options

After choosing the **status** command switch, the following options are available. Usage:

```
nsys [global-options] status [options]
```

Short	Long	Possible Parameters	Default	Switch Description
	<none>			Returns current state of the CLI.
-e	--environment			Returns information about the system regarding suitability of the profiling environment.
	--session	session identifier	none	Print the status of the indicated session. The option argument must represent a valid session name or ID as reported by <b>nsyssessions list</b> . Any <b>%q{ENV_VAR}</b> pattern will be substituted with the value of the environment variable. Any <b>%h</b> pattern will be substituted with the hostname of the system. Any <b>%</b>

Short	Long	Possible Parameters	Default	Switch Description
				% pattern will be substituted with %.

### 1.3.11. CLI Sessions Command Switch Subcommands

After choosing the **sessions** command switch, the following subcommands are available. Usage:

```
nsys [global-options] sessions [subcommand]
```

Subcommand	Description
list	List all active sessions including ID, name, and state information

## 1.4. Example Single Command Lines

### Version Information

```
nsys -v
```

Effect: Prints tool version information to the screen.

### Run with elevated privilege

```
sudo nsys profile <app>
```

Effect: Nsight Systems CLI (and target application) will run with elevated privilege. This is necessary for some features, such as FTrace or system-wide CPU sampling. If you don't want the target application to be elevated, use `--run-as` option.

### Default analysis run

```
nsys profile <application>  
[application-arguments]
```

Effect: Launch the application using the given arguments. Start collecting immediately and end collection when the application stops. Trace CUDA, OpenGL, NVTX, and OS runtime libraries APIs. Collect CPU sampling information and thread scheduling information. With Nsight Systems Embedded Platforms Edition this will only analysis the single process. With Nsight Systems Workstation Edition this will trace the process tree. Generate the report#.nsys-rep file in the default location, incrementing the report number if needed to avoid overwriting any existing output files.

### Limited trace only run

```
nsys profile --trace=cuda,nvtx -d 20  
--sample=none --cpuctxsw=none -o my_test <application>  
[application-arguments]
```

Effect: Launch the application using the given arguments. Start collecting immediately and end collection after 20 seconds or when the application ends. Trace CUDA and NVTX APIs. Do not collect CPU sampling information or thread scheduling information.

Profile any child processes. Generate the output file as `my_test.nsys-rep` in the current working directory.

### Delayed start run

```
nsys profile -e TEST_ONLY=0 -y 20
<application> [application-arguments]
```

Effect: Set environment variable `TEST_ONLY=0`. Launch the application using the given arguments. Start collecting after 20 seconds and end collection at application exit. Trace CUDA, OpenGL, NVTX, and OS runtime libraries APIs. Collect CPU sampling and thread schedule information. Profile any child processes. Generate the `report#.nsys-rep` file in the default location, incrementing if needed to avoid overwriting any existing output files.

### Collect ftrace events

```
nsys profile --ftrace=drm/drm_vblank_event
-d 20
```

Effect: Collect ftrace **drm\_vblank\_event** events for 20 seconds. Generate the `report#.nsys-rep` file in the current working directory. Note that ftrace event collection requires running as root. To get a list of ftrace events available from the kernel, run the following:

```
sudo cat /sys/kernel/debug/tracing/available_events
```

### Run GPU metric sampling on one TU10x

```
nsys profile --gpu-metrics-device=0
--gpu-metrics-set=tu10x-gfxt <application>
```

Effect: Launch application. Collect default options and GPU metrics for the first GPU (a TU10x), using the `tu10x-gfxt` metric set at the default frequency (10 kHz). Profile any child processes. Generate the `report#.nsys-rep` file in the default location, incrementing if needed to avoid overwriting any existing output files.

### Run GPU metric sampling on all GPUs at a set frequency

```
nsys profile --gpu-metrics-device=all
--gpu-metrics-frequency=20000 <application>
```

Effect: Launch application. Collect default options and GPU metrics for all available GPUs using the first suitable metric set for each and sampling at 20 kHz. Profile any child processes. Generate the `report#.nsys-rep` file in the default location, incrementing if needed to avoid overwriting any existing output files.

### Collect custom ETW trace using configuration file

```
nsys profile --etw-provider=file.JSON
```

Effect: Configure custom ETW collectors using the contents of `file.JSON`. Collect data for 20 seconds. Generate the `report#.nsys-rep` file in the current working directory.

A template JSON configuration file is located at in the Nsight Systems installation directory as `\target-windows-x64\etw_providers_template.json`. This path will show up automatically if you call

```
nsys profile --help
```

The **level** attribute can only be set to one of the following:

- `TRACE_LEVEL_CRITICAL`

- ▶ TRACE\_LEVEL\_ERROR
- ▶ TRACE\_LEVEL\_WARNING
- ▶ TRACE\_LEVEL\_INFORMATION
- ▶ TRACE\_LEVEL\_VERBOSE

The **flags** attribute can only be set to one or more of the following:

- ▶ EVENT\_TRACE\_FLAG\_ALPC
- ▶ EVENT\_TRACE\_FLAG\_CSWITCH
- ▶ EVENT\_TRACE\_FLAG\_DBGPRINT
- ▶ EVENT\_TRACE\_FLAG\_DISK\_FILE\_IO
- ▶ EVENT\_TRACE\_FLAG\_DISK\_IO
- ▶ EVENT\_TRACE\_FLAG\_DISK\_IO\_INIT
- ▶ EVENT\_TRACE\_FLAG\_DISPATCHER
- ▶ EVENT\_TRACE\_FLAG\_DPC
- ▶ EVENT\_TRACE\_FLAG\_DRIVER
- ▶ EVENT\_TRACE\_FLAG\_FILE\_IO
- ▶ EVENT\_TRACE\_FLAG\_FILE\_IO\_INIT
- ▶ EVENT\_TRACE\_FLAG\_IMAGE\_LOAD
- ▶ EVENT\_TRACE\_FLAG\_INTERRUPT
- ▶ EVENT\_TRACE\_FLAG\_JOB
- ▶ EVENT\_TRACE\_FLAG\_MEMORY\_HARD\_FAULTS
- ▶ EVENT\_TRACE\_FLAG\_MEMORY\_PAGE\_FAULTS
- ▶ EVENT\_TRACE\_FLAG\_NETWORK\_TCPIP
- ▶ EVENT\_TRACE\_FLAG\_NO\_SYSCONFIG
- ▶ EVENT\_TRACE\_FLAG\_PROCESS
- ▶ EVENT\_TRACE\_FLAG\_PROCESS\_COUNTERS
- ▶ EVENT\_TRACE\_FLAG\_PROFILE
- ▶ EVENT\_TRACE\_FLAG\_REGISTRY
- ▶ EVENT\_TRACE\_FLAG\_SPLIT\_IO
- ▶ EVENT\_TRACE\_FLAG\_SYSTEMCALL
- ▶ EVENT\_TRACE\_FLAG\_THREAD
- ▶ EVENT\_TRACE\_FLAG\_VAMAP
- ▶ EVENT\_TRACE\_FLAG\_VIRTUAL\_ALLOC

### Typical case: profile a Python script that uses CUDA

```
nsys profile --trace=cuda,cudnn,cublas,osrt,nvtx
--delay=60 python my_dnn_script.py
```

Effect: Launch a Python script and start profiling it 60 seconds after the launch, tracing CUDA, cuDNN, cuBLAS, OS runtime APIs, and NVTX as well as collecting thread schedule information.

### Typical case: profile an app that uses Vulkan

```
nsys profile --trace=vulkan,osrt,nvtx
--delay=60 ./myapp
```

Effect: Launch an app and start profiling it 60 seconds after the launch, tracing Vulkan, OS runtime APIs, and NVTX as well as collecting CPU sampling and thread schedule information.

## 1.5. Example Interactive CLI Command Sequences


### Collect from beginning of application, end manually

```
nsys start --stop-on-exit=false
nsys launch --trace=cuda,nvtx --sample=none <application> [application-
arguments]
nsys stop
```

Effect: Create interactive CLI process and set it up to begin collecting as soon as an application is launched. Launch the application, set up to allow tracing of CUDA and NVTX as well as collection of thread schedule information. Stop only when explicitly requested. Generate the report#`.nsys-rep` in the default location.

**Note:**


If you start a collection and fail to stop the collection (or if you are allowing it to stop on exit, and the application runs for too long) your system's storage space may be filled with collected data



### Run application, begin collection manually, run until process ends

```
nsys launch -w true <application> [application-arguments]
nsys start
```

Effect: Create interactive CLI and launch an application set up for default analysis. Send application output to the terminal. No data is collected until you manually start collection at area of interest. Profile until the application ends. Generate the report#.`nsys-rep` in the default location.






before  
start  
is  
called  
Nsight  
Systems  
will  
create  
a  
fully  
formed .nsys-  
rep  
file  
containing  
no  
data.

### Run application, start/stop collection using cudaProfilerStart/Stop

```
nsys start -c cudaProfilerApi
nsys launch -w true <application> [application-arguments]
```

Effect: Create interactive CLI process and set it up to begin collecting as soon as a `cudaProfilerStart()` is detected. Launch application for default analysis, sending application output to the terminal. Stop collection at next call to `cudaProfilerStop`, when the user calls **nsys stop**, or when the root process terminates. Generate the report#.nsys-rep in the default location.



Note:

If  
you  
call  
**nsys  
launch**  
before  
**nsys  
start**  
-  
c  
**cudaProfilerApi**  
and  
the  
code  
contains  
a  
large  
number  
of  
short  
duration  
`cudaProfilerStart/  
Stop`  
pairs,  
Nsight  
Systems  
may  
be  
unable

to process them correctly, causing a fault. This will be corrected in a future version.


**Note:** The Nsight Systems CLI does not support multiple calls to the `cudaProfilerStart/Stop` API at this time.

### Run application, start/stop collection using NVTX

```
nsys start -c nvtx
nsys launch -w true -p MESSAGE@DOMAIN <application> [application-arguments]
```

Effect: Create interactive CLI process and set it up to begin collecting as soon as an NVTX range with given message in given domain (capture range) is opened. Launch application for default analysis, sending application output to the terminal. Stop collection when all capture ranges are closed, when the user calls **nsys stop**, or when the root process terminates. Generate the `report#.nsys-rep` in the default location.

**Note:** The Nsight Systems CLI only triggers the profiling session



NVTX capture range can be specified:

- ▶ **Message@Domain:** All ranges with given message in given domain are capture ranges. For example:

```
nsys launch -w true -p profiler@service ./app
```

This would make the profiling start when the first range with message "profiler" is opened in domain "service".

- ▶ **Message@\*:** All ranges with given message in all domains are capture ranges. For example:

```
nsys launch -w true -p profiler@* ./app
```

This would make the profiling start when the first range with message "profiler" is opened in any domain.

- ▶ **Message:** All ranges with given message in default domain are capture ranges. For example:

```
nsys launch -w true -p profiler ./app
```

This would make the profiling start when the first range with message "profiler" is opened in the default domain.

- ▶ By default only messages, provided by NVTX registered strings are considered to avoid additional overhead. To enable non-registered strings check please launch your application with **NSYS\_NVTX\_PROFILER\_REGISTER\_ONLY=0** environment:


```
nsys launch -w true -p profiler@service -e  
NSYS_NVTX_PROFILER_REGISTER_ONLY=0 ./app
```

## Run application, start/stop collection multiple times

The interactive CLI supports multiple sequential collections per launch.

```
nsys launch <application> [application-arguments]  
nsys start  
nsys stop  
nsys start  
nsys stop  
nsys shutdown --kill sigkill
```

Effect: Create interactive CLI and launch an application set up for default analysis. Send application output to the terminal. No data is collected until the start command is executed. Collect data from start until stop requested, generate report#.qstrm in the current working directory. Collect data from second start until the second stop request, generate report#.nsys-rep (incremented by one) in the current working directory. Shutdown the interactive CLI and send sigkill to the target application's process group.





## 1.6. Example Stats Command Sequences

### Display default statistics

```
nsys stats report1.nsys-rep
```

Effect: Export an SQLite file named `report1.sqlite` from `report1.nsys-rep` (assuming it does not already exist). Print the default reports in column format to the console.

Note: The following two command sequences should present very similar information:

```
nsys profile --stats=true <application>
```

or

```
nsys profile <application>
```

```
nsys stats report1.nsys-rep
```

### Display specific data from a report

```
nsys stats --report gputrace report1.nsys-rep
```

Effect: Export an SQLite file named `report1.sqlite` from `report1.nsys-rep` (assuming it does not already exist). Print the report generated by the `gputrace` script to the console in column format.

### Generate multiple reports, in multiple formats, output multiple places

```
nsys stats --report gputrace --report gpukernsum --report cudaapisum  
--format csv,column --output .,- report1.nsys-rep
```

Effect: Export an SQLite file named `report1.sqlite` from `report1.nsys-rep` (assuming it does not already exist). Generate three reports. The first, the `gputrace` report, will be output to the file `report1_gputrace.csv` in CSV format. The other two reports, `gpukernsum` and `cudaapisum`, will be output to the console as columns of data. Although three reports were given, only two formats and outputs are given. To reconcile this, both the list of formats and outputs is expanded to match the list of reports by repeating the last element.

### Submit report data to a command

```
nsys stats --report cudaapisum --format table \ --output @"grep -E  
(-|Name|cudaFree" test.sqlite
```

Effect: Open test.sqlite and run the `cudaapisum` script on that file. Generate table data and feed that into the command `grep -E (-|Name|cudaFree)`. The `grep` command will filter out everything but the header, formatting, and the `cudaFree` data, and display the results to the console.

Note: When the output name starts with @, it is defined as a command. The command is run, and the output of the report is piped to the command's stdin (standard-input). The command's stdout and stderr remain attached to the console, so any output will be displayed directly to the console.

Be aware there are some limitations in how the command string is parsed. No shell expansions (including \*, ?, [], and ~) are supported. The command cannot be piped to another command, nor redirected to a file using shell syntax. The command and command arguments are split on whitespace, and no quotes (within the command syntax) are supported. For commands that require complex command line syntax, it is suggested that the command be put into a shell script file, and the script designated as the output command

## 1.7. Example Output from --stats Option

The `nsys stats` command can be used post analysis to generate specific or personalized reports. For a default fixed set of summary statistics to be automatically generated, you can use the `--stats` option with the `nsys profile` or `nsys start` command to generate a fixed set of useful summary statistics.

If your run traces CUDA, these include CUDA API, Kernel, and Memory Operation statistics:

```

Generating cuda API Statistics...
cuda API Statistics

```

Time(%)	Time (ns)	Calls	Avg (ns)	Min (ns)	Max (ns)	Name
73.0	1858829425	404	4601062.9	131864	18705795	cudaMemcpy
11.3	287212369	1	287212369.0	287212369	287212369	cudaMalloc3DArray
4.3	108862768	2215	49148.0	3478	15493937	cudaGraphicsMapResources
3.3	84097966	202	416326.6	258148	2046180	cudaMalloc
3.0	75687195	201	376553.2	167486	1559709	cudaFree
2.1	54669996	2215	24681.7	3261	17194720	cudaGraphicsUnmapResources
1.5	37697367	4221	8930.9	5532	71517	cudaLaunch
1.4	36258561	202	179497.8	5441	737046	cudaMemcpyToSymbol
0.1	1961207	5	392241.4	350245	490291	cudaGraphicsGLRegisterBuffer
0.0	661494	4221	156.7	94	4855	cudaConfigureCall
0.0	469750	1	469750.0	469750	469750	cudaMemcpy3D
0.0	6513	1	6513.0	6513	6513	cudaBindTextureToArray

```

Generating cuda Kernel and Memory Operation Statistics...
cuda Kernel Statistics

```

Time(%)	Time (ns)	Instances	Avg (ns)	Min (ns)	Max (ns)	Name
38.2	20957543	1206	17377.7	9152	42272	DeviceRadixSortDownsweepKernel
36.3	19951318	1206	16543.4	15808	20961	RadixSortScanBinsKernel
13.4	7381869	1206	6121.0	3936	11776	DeviceRadixSortUpsweepKernel
12.0	6605490	603	10954.4	1920	25536	_kernel_agent

```

cuda Memory Operation Statistics (time)

```

Time(%)	Time (ns)	Operations	Avg (ns)	Min (ns)	Max (ns)	Name
71.9	1080910	606	1783.7	832	91361	[CUDA memcpy HtoD]
28.1	421799	1	421799.0	421799	421799	[CUDA memcpy HtoA]

```

cuda Memory Operation Statistics (bytes)

```

Total Bytes (KB)	Operations	Avg (KB)	Min (bytes)	Max (KB)	Name
5184.0	606	8.5551	52	1024.0	[CUDA memcpy HtoD]
4096.0	1	4096.0	4194304	4096.0	[CUDA memcpy HtoA]

If your run traces OS runtime events or NVTX push-pop ranges:

Generating Operating System Runtime API Statistics...						
Operating System Runtime API Statistics						
Time(%)	Time (ns)	Calls	Avg (ns)	Min (ns)	Max (ns)	Name
33.8	7780422146	388	20052634.4	1021	101325794	poll
32.5	7486252249	84	89122050.6	18165	100621271	sem_timedwait
30.4	7001017913	14	500072708.1	500054528	500094119	pthread_cond_timedwait
3.0	691921867	2879	240334.1	1000	16503430	ioctl
0.1	20746589	2156	9622.7	4703	43645	fgets
0.1	15236506	275	55405.5	1021	14452991	recvmsg
0.0	5341120	456	11713.0	1122	258129	fopen
0.0	3961960	284	13950.6	1000	91521	mmap
0.0	3660301	435	8414.5	1457	27680	fclose
0.0	1959097	246	7963.8	2252	69097	munmap
0.0	1020789	194	5261.8	2068	19845	open64
0.0	841520	489	1720.9	1000	16808	sched_yield
0.0	623388	40	15584.7	1007	50469	read
0.0	582336	158	3685.7	1289	78529	recv
0.0	279456	80	3493.2	1111	18551	writev
0.0	149645	64	2338.2	1214	10598	open
0.0	144462	5	28892.4	22780	39774	pthread_create
0.0	139762	15	9317.5	1118	77744	fread
0.0	52949	13	4073.0	1341	9112	mprotect
0.0	38777	9	4308.6	2443	10141	write
0.0	22994	4	5748.5	4763	6798	socket
0.0	21060	4	5265.0	4674	5925	sendmsg
0.0	18287	4	4571.7	2795	7277	socketpair
0.0	16881	3	5627.0	2390	7615	connect
0.0	12617	5	2523.4	1157	3926	mmap64
0.0	11368	3	3789.3	2270	5849	pipe2
0.0	11014	2	5507.0	4484	6530	pthread_cond_signal
0.0	5121	1	5121.0	5121	5121	fopen64
0.0	5118	3	1706.0	1086	2945	fcntl
0.0	4102	1	4102.0	4102	4102	shutdown
0.0	3587	1	3587.0	3587	3587	lockf
0.0	1744	1	1744.0	1744	1744	bind
0.0	1007	1	1007.0	1007	1007	fflush
Generating NVTX Push-Pop Range Statistics...						
NVTX Push-Pop Range Statistics						
Time(%)	Time (ns)	Instances	Avg (ns)	Min (ns)	Max (ns)	Range
93.2	6856491504	201	34111898.0	6935189	285693359	frame
6.8	499693190	201	2486035.8	1874225	31362835	render

If your run traces graphics debug markers these include DX11 debug markers, DX12 debug markers, Vulkan debug markers or KHR debug markers:

Running [D:\src\output\_host\Built\Bin\QuadD-Release\target-windows-x64\reports\vulkanmarkersum.py D:\src\output\_host\Built\Bin\QuadD-Release\target-windows-x64\marker\_test\ued\_infiltrator\_vulkan\_markers.sqlite]...

Time(%)	Total Time (ns)	Instances	Average (ns)	Minimum (ns)	Maximum (ns)	StdDev	Range
37.2	2335018401	136	17169252.9	13692647	28504631	2729172.8	SendAllEndOffFrameUpdates
10.7	670082802	137	4891115.3	1711561	283744644	24611148.8	BasePass
5.0	311897629	1507	206965.9	6198	3407757	215626.1	BeginRenderingBuffer
3.2	198278098	1644	120608.1	3128	952334	152230.7	BeginRenderingTranslucency
3.0	186977118	137	1364796.5	1066597	4088690	395358.6	Lights
3.0	186626496	137	1362237.2	1064426	4084884	395189.6	DirectLighting
1.7	104681274	137	764896.9	592935	2607777	238923.8	NonShadowedLights
1.5	95597952	136	702926.1	538868	1944515	269677.7	PostProcessing
1.4	85533857	137	624334.7	432949	2359711	243159.6	PrePass DDM_Allopaque (Forced by DBuffer)
1.3	83827427	2820	29726.0	1514	755373	43994.7	BeginRenderingPrePass
1.3	81222414	137	592871.6	441855	1876511	186280.9	ShadowedLights
1.3	81108377	1777	45638.9	4951	1541354	115928.7	StandardDeferredLighting
1.3	80751508	2462	32799.2	2085	1529342	99702.1	BeginRenderingSceneColor
1.1	70866836	276	256763.9	16488	2145669	291073.5	BeginSeparateTranslucency
1.0	61329202	19591	3130.5	1228	319829	4991.0	M_FogSheet_Master_SF_FogSheet_Plane
0.8	52655480	1914	27510.7	2400	734665	60946.1	InjectTranslucentLightArray
0.8	50038202	14125	3542.5	1362	281286	5669.2	M_GodRay_MASTER_SF_GodRay_Plane
0.7	43028473	137	314694.5	231792	1803868	103224.0	InjectNonShadowedTranslucentLighting
0.6	37774169	96	393480.9	323525	550130	37746.8	UpdatedRUScene PrimitivesToUpdate and Offset = 48 0
0.6	37313346	548	68090.0	23621	252291	39130.9	GPUParticles SimulateAndClear
0.6	37119090	273	135967.4	10130	4930980	389044.2	RenderVelocities
0.6	34849906	136	255249.3	192556	597254	92451.7	DOF (Alpha-No)
0.5	32798709	332	98767.2	13863	1703854	187206.8	VIS_ArtDemo_Screw_SpotLightStationary_7
0.5	29069102	137	212183.2	161573	539013	56026.7	GPUParticles_PreRender
0.4	25741368	411	62631.1	28555	342351	38492.3	ShadowProjectionOnOpaque
0.4	24154169	136	177694.2	130608	594279	86681.5	Bloom
0.4	23310271	548	42537.0	9120	201856	30514.7	ParticleSimulation
0.4	23121491	411	56256.7	24857	333976	35675.2	RenderShadowProjection
0.4	20399125	137	167438.9	137646	492316	45670.7	LightCompositionTasks_Prelighting
0.4	22779500	6850	3325.5	1493	203231	4384.5	Environment_Wire_MASTER_SF_Wires_02
0.3	21179479	137	154594.7	107090	1582286	133950.6	ViewOcclusionTests 0
0.3	21058892	274	76857.3	13489	447949	74050.6	VIS_ArtDemo_Screw_SF_Infil_Underground_Pipe01_439
0.3	20156748	137	147444.1	104452	1754719	149998.6	ShadowDepths
0.3	19368869	410	47241.1	5325	435358	62128.4	VelocityRendering
0.3	18867829	137	137721.4	100037	1745961	146450.6	Atlas0 2048x2048
0.3	17336627	820	21142.2	10371	119580	13048.1	InjectTranslucentVolume
0.3	17278644	137	126120.9	87753	1551792	130700.7	IndividualQueries
0.3	15776024	274	57576.7	21847	210442	33293.9	ParticleSimulationCommands
0.2	15631413	274	57849.0	13915	364140	49448.6	VIS_ArtDemo_Screw_SpotLightStationary_30
0.2	13147425	685	19193.3	10046	383482	16959.3	ShadowRectClasses
0.2	12826154	136	94310.0	69204	1305919	189278.5	Distortion
0.2	12029306	821	14652.0	8142	237658	13625.1	Skinning000 Chunk0 InStreamStart0 OutStart0 Verts0021 Morph0/0
0.2	11313758	2740	4129.1	1377	54848	4497.1	M_CloudSheetMaster EditorPlane
0.2	11128575	135	82274.6	61380	311120	33641.8	VIS_ArtDemo_Keyhole_SpotLightStationary_2
0.2	10845277	1507	7196.6	3515	174162	6173.2	@Buffer
0.2	10647885	25	425915.4	338156	962796	122138.9	UpdatedRUScene PrimitivesToUpdate and Offset = 47 0
0.2	10420894	137	76064.9	57156	206479	20830.7	ComputeLightGrid

Recipes for these statistics as well as documentation on how to create your own metrics will be available in a future version of the tool.

## 1.8. Importing and Viewing Command Line Results Files


The CLI generates a .qdstrm file. The .qdstrm file is an intermediate result file, not intended for multiple imports. It needs to be processed, either by importing it into the GUI or by using the standalone QdstrmImporter to generate an optimized .nsys-rep file. Use this .nsys-rep file when re-opening the result on the same machine, opening the result on a different machine, or sharing results with teammates.

This version of Nsight Systems will attempt to automatically convert the .qdstrm file to a .nsys-rep file with the same name after the run finishes if the required libraries are available. The ability to turn off auto-conversion will be added in a later version.

### Import Into the GUI

The CLI and host GUI versions must match to import a .qdstrm file successfully. The host GUI is backward compatible only with .nsys-rep files.

Copy the .qdstrm file you are interested in viewing to a system where the Nsight Systems host GUI is installed. Launch the Nsight Systems GUI. Select **File->Import...** and choose the .qdstrm file you wish to open.



The import of really large, multi-gigabyte, .qdstrm files may take up all of the memory on the host computer and lock up the system. This will be fixed in a later version.

### Importing Windows ETL files

For Windows targets, ETL files captured with Xperf or the `log.cmd` command supplied with GPUView in the Windows Performance Toolkit can be imported to create reports as if they were captured with Nsight Systems's "WDDM trace" and "Custom ETW trace" features. Simply choose the .etl file from the Import dialog to convert it to a .nsys-rep file.

### Create .nsys-rep Using QdstrmImporter

The CLI and QdstrmImporter versions must match to convert a .qdstrm file into a .nsys-rep file. This .nsys-rep file can then be opened in the same version or more recent versions of the GUI.

To run QdstrmImporter on the host system, find the QdstrmImporter binary in the Host-x86\_64 directory in your installation. QdstrmImporter is available for all host platforms. See options below.

To run QdstrmImporter on the target system, copy the Linux Host-x86\_64 directory to the target Linux system or install Nsight Systems for Linux host directly on the target. The Windows or macOS host QdstrmImporter will not work on a Linux Target. See options below.

Short	Long	Parameter	Description
-h	--help		Help message providing information about available options and their parameters.
-v	--version		Output QdstrmImporter version information
-i	--input-file	filename or path	Import .qdstrm file from this location.
-o	--output-file	filename or path	Provide a different file name or path for the resulting .nsys-

Short	Long	Parameter	Description
			rep file. Default is the same name and path as the .qdstm file

## 1.9. Using the CLI to Analyze MPI Codes

### 1.9.1. Tracing MPI API calls

The Nsight Systems CLI has built-in API trace support via `--trace=mpi` option only for the OpenMPI and MPICH implementations of MPI. It traces a default list of synchronous MPI APIs. If you require more control over the list of traced APIs or if you are using a different MPI implementation, see [github nvtx pmpi wrappers](#).

You can use this documentation to generate a shared object to wrap a list of synchronous MPI APIs with NVTX using the MPI profiling interface (PMPI). If you set your `LD_PRELOAD` environment variable to the path of that object, nsys will capture and report the MPI API trace information when `--trace=nvtx` is used. There is no need to use `--trace=MPI`.

NVTX tracing is automatically enabled when MPI trace is turned on.

### 1.9.2. Using the CLI to Profile Applications Launched with mpirun

This version of the Nsight Systems CLI supports concurrent use of the `nsys profile` command. Each instance will create a separate report file.

You cannot use multiple instances of the interactive CLI concurrently, or use the interactive CLI concurrently with `nsys profile` in this version.

Nsight Systems can be used to profile applications launched with `mpirun` command. Since concurrent use of the CLI is supported only when using the `nsys profile` command, Nsight Systems cannot profile each node from the GUI or from the interactive CLI.

To profile everything, putting the data in one file:

```
nsys [nsys options] mpirun [mpi options]
```

To profile everything putting the data from each rank into a separate file:

```
mpirun [mpi options] nsys profile [nsys options]
```

To profile a single MPI process use a wrapper script. The following script(called "wrap.sh") runs nsys on rank 0 only:

```
#!/bin/bash
if [[ $OMPI_COMM_WORLD_RANK == 0 ]]; then
~/nsys/nsys_profile ./myapp "$@" --mydummyargument
else
./myapp "$@"
fi
```

and then execute **mpirun ./wrap.sh**.

**Note:**

Currently you will need a dummy argument to the process, so that Nsight Systems can decide which process to profile. This means that your process must accept dummy arguments to take advantage of this workaround. This script as written is for Open MPI, but should be easily

	adaptable to other MPI implementations.
--	---

# Chapter 2.


## PROFILING FROM THE GUI

### 2.1. Profiling Linux Targets from the GUI


#### 2.1.1. Connecting to the Target Device

Nsight Systems provides a simple interface to profile on localhost or manage multiple connections to Linux or Windows based devices via SSH. The network connections manager can be launched through the device selection dropdown:


On x86\_64:



On Tegra:



The dialog has simple controls that allow adding, removing, and modifying connections:



**Security notice:** SSH is only used to establish the initial connection to a target device, perform checks, and upload necessary files. The actual profiling commands and data are transferred through a raw, unencrypted socket. Nsight Systems should not be used in a network setup where attacker-in-the-middle attack is possible, or where untrusted parties may have network access to the target device.

While connecting to the target device, you will be prompted to input the user's password. Please note that if you choose to remember the password, it will be stored in plain text in the configuration file on the host. Stored passwords are bound to the public key fingerprint of the remote device.

The **No authentication** option is useful for devices configured for passwordless login using **root** username. To enable such a configuration, edit the file **/etc/ssh/sshd\_config** on the target and specify the following option:

```
PermitRootLogin yes
```

Then set empty password using **passwd** and restart the SSH service with **service ssh restart**.

**Open ports:** The Nsight Systems daemon requires port 22 and port 45555 to be open for listening. You can confirm that these ports are open with the following command:

```
sudo firewall-cmd --list-ports --permanent
sudo firewall-cmd --reload
```

To open a port use the following command, skip **--permanent** option to open only for this session:

```
sudo firewall-cmd --permanent --add-port 45555/tcp
sudo firewall-cmd --reload
```

Likewise, if you are running on a cloud system, you must open port 22 and port 45555 for ingress.

**Kernel Version Number** - To check for the version number of the kernel support of Nsight Systems on a target device, run the following command on the remote device:

```
cat /proc/quadd/version
```

Minimal supported version is 1.82.

Additionally, presence of Netcat command (**nc**) is required on the target device. For example, on Ubuntu this package can be installed using the following command:

```
sudo apt-get install netcat-openbsd
```


## 2.1.2. System-Wide Profiling Options

### 2.1.2.1. Linux x86\_64


System-wide profiling is available on x86 for Linux targets only when run with root privileges.

#### Ftrace Events Collection

Select Ftrace events




Choose which events you would like to collect.



## GPU Context Switch Trace


Tracing of context switching on the GPU is enabled with driver r435.17 or higher.



Here is a screenshot showing three CUDA kernels running simultaneously in three different CUDA contexts on a single GPU.



### 2.1.2.2. Linux for Tegra




**Trace all processes** – On compatible devices (with kernel module support version 1.107 or higher), this enables trace of all processes and threads in the system. Scheduler events from all tasks will be recorded.

**Collect PMU counters** – This allows you to choose which PMU (Performance Monitoring Unit) counters Nsight Systems will sample. Enable specific counters when interested in correlating cache misses to functions in your application.

### 2.1.3. Target Sampling Options

Target sampling behavior is somewhat different for Nsight Systems Workstation Edition and Nsight Systems Embedded Platforms Edition.


#### Target Sampling Options for Workstation



Three different backtrace collections options are available when sampling CPU instruction pointers. Backtraces can be generated using Intel (c) Last Branch Record (LBR) registers. LBR backtraces generate minimal overhead but the backtraces have

limited depth. Backtraces can also be generated using DWARF debug data. DWARF backtraces incur more overhead than LBR backtraces but have much better depth. Finally, backtraces can be generated using frame pointers. Frame pointer backtraces incur medium overhead and have good depth but only resolve frames in the portions of the application and its libraries (including 3rd party libraries) that were compiled with frame pointers enabled. Normally, frame pointers are disabled by default during compilation.

By default, Nsight Systems will use Intel(c) LBRs if available and fall back to using dwarf unwind if they are not. **Choose modes...** will allow you to override the default.




The **Include child processes** switch controls whether API tracing is only for the launched process, or for all existing and new child processes of the launched process. If you are running your application through a script, for example a bash script, you need to set this checkbox.

The **Include child processes** switch does not control sampling in this version of Nsight Systems. The full process tree will be sampled regardless of this setting. This will be fixed in a future version of the product.

Nsight Systems can sample one process tree. Sampling here means interrupting each processor after a certain number of events and collecting an instruction pointer (IP)/backtrace sample if the processor is executing the profilee.

When sampling the CPU on a workstation target, Nsight Systems traces thread context switches and infers thread state as either Running or Blocked. Note that Blocked in the timeline indicates the thread may be Blocked (Interruptible) or Blocked (Uninterruptible). Blocked (Uninterruptible) often occurs when a thread has transitioned into the kernel and cannot be interrupted by a signal. Sampling can be enhanced with OS runtime libraries tracing; see [OS Runtime Libraries Trace](#) for more information.

## Target Sampling Options for Embedded Linux




Currently Nsight Systems can only sample one process. Sampling here means that the profilee will be stopped periodically, and backtraces of active threads will be recorded.

Most applications use stripped libraries. In this case, many symbols may stay unresolved. If unstripped libraries exist, paths to them can be specified using the **Symbol locations...** button. Symbol resolution happens on host, and therefore does not affect performance of profiling on the target.

Additionally, debug versions of ELF files may be picked up from the target system. Refer to [Debug Versions of ELF Files](#) for more information.

## 2.1.4. Hotkey Trace Start/Stop

Nsight Systems Workstation Edition can use hotkeys to control profiling. Press the hotkey to start and/or stop a trace session from within the target application's graphic window. This is useful when tracing games and graphic applications that use fullscreen display. In these scenarios switching to Nsight Systems' UI would unnecessarily introduce the window manager's footprint into the trace. To enable the use of Hotkey check the Hotkey checkbox in the project settings page:



The default hotkey is F12.


## 2.1.5. Launching and Attaching to Processes

Nsight Systems Embedded Platforms Edition can work with Linux-based devices in three modes:

1. Attaching to a process by name
2. Attaching to a process by name, or launching a new process
3. Attaching to a process by its PID

The purpose of the configuration here is to define which process the profiler will attach to for sampling and tracing. Additionally, the profiler can launch a process prior to attaching to it, ensuring that all environment variables are set correctly to successfully collect trace information.

In **Attach only** mode, the process is selected by its name and command line arguments, as visible using the **ps** tool.




In **Attach or launch** mode, the process is to first search as if in the Attach only mode, but if it is not found, the process is launched using the same path and command line arguments. If NVTX, CUDA, or other trace settings are selected, the process will be automatically launched with appropriate environment variables.

Note that in some cases, the capabilities of Nsight Systems are not sufficient to correctly launch the application; for example, if certain environment variables have to be corrected. In this case, the application has to be started manually and Nsight Systems should be used in Attach only mode.

The **Edit arguments...** link will open an editor window, where every command line argument is edited on a separate line. This is convenient when arguments contain spaces or quotes.

To properly populate the **Search criteria** field based on a currently running process on the target system, use the **Select a process** button on the right, which has ellipsis as the caption. The list of processes is automatically refreshed upon opening.



**Attach by PID** mode should be used to connect to a specific process.

To choose one of the currently running processes on the target system, use the **Select a process** button on the right.

## 2.2. Profiling Windows Targets from the GUI

Profiling on Windows devices is similar to the profiling on Linux devices. Please refer to the [Profiling Linux Targets from the GUI](#) section for the detailed documentation and connection information. The major differences on the platforms are listed below:


### Remoting to a Windows Based Machine

To perform remote profiling to a target Windows based machines, [install and configure an OpenSSH Server on the target machine](#).

### Hotkey Trace Start/Stop

Nsight Systems Workstation Edition can use hotkeys to control profiling. Press the hotkey to start and/or stop a trace session from within the target application's graphic

window. This is useful when tracing games and graphic applications that use fullscreen display. In these scenarios switching to Nsight Systems' UI would unnecessarily introduce the window manager's footprint into the trace. To enable the use of Hotkey check the Hotkey checkbox in the project settings page:



The default hotkey is F12.

**Changing the Default Hotkey Binding** - A different hotkey binding can be configured by setting the HotKeyIntValue configuration field in the config.ini file.


Set the decimal numeric identifier of the hotkey you would like to use for triggering start/stop from the target app graphics window. The default value is 123 which corresponds to 0x7B, or the F12 key.

Virtual key identifiers are detailed in [MSDN's Virtual-Key Codes](#).


Note that you must convert the hexadecimal values detailed in this page to their decimal counterpart before using them in the file. For example, to use the F1 key as a start/stop trace hotkey, use the following settings in the config.ini file:

```
HotKeyIntValue=112
```

## Target Sampling Options on Windows



Nsight Systems can sample one process tree. Sampling here means interrupting each processor periodically. The sampling rate is defined in the project settings and is either 100Hz, 1KHz (default value), 2KHz, 4KHz, or 8KHz.




On Windows, Nsight Systems can collect thread activity of one process tree. Collecting thread activity means that each thread context switch event is logged and (optionally) a backtrace is collected at the point that the thread is scheduled back for execution. Thread states are displayed on the timeline.

If it was collected, the thread backtrace is displayed when hovering over a region where the thread execution is blocked.

## Symbol Locations

Symbol resolution happens on host, and therefore does not affect performance of profiling on the target.

Press the **Symbol locations...** button to open the **Configure debug symbols location** dialog.



Use this dialog to specify:

- ▶ Paths of PDB files
- ▶ Symbols servers
- ▶ The location of the local symbol cache

To use a symbol server:

1. Install **Debugging Tools for Windows**, a part of the [Windows 10 SDK](#).
2. Add the symbol server URL using the **Add Server** button.

Information about Microsoft's public symbol server, which enables getting Windows operating system related debug symbols can be found [here](#).

## 2.3. Profiling QNX Targets from the GUI

Profiling on QNX devices is similar to the profiling on Linux devices. Please refer to the [Profiling Linux Targets from the GUI](#) section for the detailed documentation. The major differences on the platforms are listed below:

- ▶ Backtrace sampling is not supported. Instead backtraces are collected for long OS runtime libraries calls. Please refer to the [OS Runtime Libraries Trace](#) section for the detailed documentation.
- ▶ CUDA support is limited to CUDA 9.0+
- ▶ Filesystem on QNX device might be mounted read-only. In that case Nsight Systems is not able to install target-side binaries, required to run the profiling session. Please make sure that target filesystem is writable before connecting to QNX target. For example, make sure the following command works:

```
echo XX > /xx && ls -l /xx
```

# Chapter 3.

## EXPORT FORMATS

### 3.1. SQLite Schema Reference

Nsight Systems has the ability to export SQLite database files from the .nsys-rep results file. From the CLI, use **nsys export**. From the GUI, call **File->Export...**

**Note:** The .nsys-rep report format is the only data format for Nsight Systems that should be considered forward compatible. The SQLite schema can and will change in the future.

The schema for a concrete database can be obtained with the sqlite3 tool built-in command **.schema**. The sqlite3 tool can be located in the Target or Host directory of your Nsight Systems installation.

**Note:** Currently tables are created lazily, and therefore not every table described in the documentation will be present in a particular database. This will change in a future version of the product. If you want a full schema of all possible tables, use **nsys export --lazy=false** during export phase.

Currently, a table is created for each data type in the exported database. Since usage patterns for exported data may vary greatly and no default use cases have been established, no indexes or extra constraints are created. Instead, refer to the SQLite Examples section for a list of common recipes. This may change in a future version of the product.

To check the version of your exported SQLite file, check the value of **EXPORT\_SCHEMA\_VERSION** in the **EXPORT\_META\_DATA** table. The schema version is a common three-value major/minor/micro version number. The first value, or major value, indicates the overall format of the database, and is only changed if there is a major re-write or re-factor of the entire database format. It is assumed that if the major version changes, all scripts or queries will break. The middle, or minor, version is changed anytime there is a more localized, but potentially breaking change, such as renaming an existing column, or changing the type of an existing column. The last, or micro version is changed any time there are additions, such as a new table or column, that should not introduce any breaking change when used with well-written, best-practices queries.

This is the schema as of the 2021.5 release, schema version 2.7.1.

```

CREATE TABLE StringIds (
  -- Consolidation of repetitive string values.

  id                      INTEGER    NOT NULL    PRIMARY KEY,      -- ID
  reference value.
  value                   TEXT       NOT NULL                                -- String
  value.
);
CREATE TABLE ThreadNames (
  nameId                  INTEGER    NOT NULL    REFERENCES StringIds(id),
  -- StringId of the thread name.
  priority                INTEGER,
  Priority of the thread.
  globalTid               INTEGER
  Serialized GlobalId.
);
CREATE TABLE ProcessStreams (
  globalPid               INTEGER    NOT NULL,
  Serialized GlobalId.
  filenameId              INTEGER    NOT NULL    REFERENCES StringIds(id),
  -- StringId of the file name.
  contentId               INTEGER    NOT NULL    REFERENCES StringIds(id) --
  StringId of the stream content.
);
CREATE TABLE TARGET_INFO_SYSTEM_ENV (
  globalVid               INTEGER    NOT NULL,
  Serialized GlobalId.
  devStateName            TEXT       NOT NULL,
  state name.
  name                    TEXT       NOT NULL,
  Property name.
  nameEnum                INTEGER    NOT NULL,
  Property enum value.
  value                   TEXT       NOT NULL
  Property value.
);
CREATE TABLE TARGET_INFO_SESSION_START_TIME (
  utcEpochNs             INTEGER,
  Epoch timestamp at start of the capture (ns).
  utcTime                 TEXT,
  of the capture in UTC.
  localTime               TEXT
  of the capture in local time of target.
);
CREATE TABLE ANALYSIS_DETAILS (
  -- Details about the analysis session.

  globalVid               INTEGER    NOT NULL,
  Serialized GlobalId.
  duration                 INTEGER    NOT NULL,
  total time span of the entire trace (ns).
  startTime               INTEGER    NOT NULL,
  start timestamp in nanoseconds.
  stopTime                INTEGER    NOT NULL
  stop timestamp in nanoseconds.
);
CREATE TABLE TARGET_INFO_GPU (
  vmId                    INTEGER    NOT NULL,
  Serialized GlobalId.
  id                       INTEGER    NOT NULL,
  ID.
  name                     TEXT,
  name.
  busLocation              TEXT,
  bus location.
  isDiscrete               INTEGER,
  if discrete, false if integrated.
  l2CacheSize              INTEGER,
  of L2 cache (B).
  totalMemory              INTEGER,
  amount of memory on the device (B).
  memoryBandwidth          INTEGER,
  of memory transferred (B).

```

## 3.2. SQLite Schema Event Values

Here are the set values stored in enums in the Nsight Systems SQLite schema

### CUDA Event Class Values

```
0 - TRACE_PROCESS_EVENT_CUDA_RUNTIME
1 - TRACE_PROCESS_EVENT_CUDA_DRIVER
13 - TRACE_PROCESS_EVENT_CUDA_EGL_DRIVER
28 - TRACE_PROCESS_EVENT_CUDNN
29 - TRACE_PROCESS_EVENT_CUBLAS
33 - TRACE_PROCESS_EVENT_CUDNN_START
34 - TRACE_PROCESS_EVENT_CUDNN_FINISH
35 - TRACE_PROCESS_EVENT_CUBLAS_START
36 - TRACE_PROCESS_EVENT_CUBLAS_FINISH
67 - TRACE_PROCESS_EVENT_CUDABACKTRACE
77 - TRACE_PROCESS_EVENT_CUDA_GRAPH_NODE_CREATION
```

See [CUPTI documentation](#) for detailed information on collected event and data types.

### NVTX Event Type Values

```
33 - NvtxCategory
34 - NvtxMark
39 - NvtxThread
59 - NvtxPushPopRange
60 - NvtxStartEndRange
75 - NvtxDomainCreate
76 - NvtxDomainDestroy
```

The difference between text and textId columns is that if an NVTX event message was passed via call to `nvtxDomainRegisterString` function, then the message will be available through textId field, otherwise the text field will contain the message if it was provided.

### OpenGL Events

#### KHR event class values

```
62 - KhrDebugPushPopRange
63 - KhrDebugGpuPushPopRange
```

#### KHR source kind values

```
0x8249 - GL_DEBUG_SOURCE_THIRD_PARTY
0x824A - GL_DEBUG_SOURCE_APPLICATION
```

## KHR type values

```
0x824C - GL_DEBUG_TYPE_ERROR
0x824D - GL_DEBUG_TYPE_DEPRECATED_BEHAVIOR
0x824E - GL_DEBUG_TYPE_UNDEFINED_BEHAVIOR
0x824F - GL_DEBUG_TYPE_PORTABILITY
0x8250 - GL_DEBUG_TYPE_PERFORMANCE
0x8251 - GL_DEBUG_TYPE_OTHER
0x8268 - GL_DEBUG_TYPE_MARKER
0x8269 - GL_DEBUG_TYPE_PUSH_GROUP
0x826A - GL_DEBUG_TYPE_POP_GROUP
```

## KHR severity values

```
0x826B - GL_DEBUG_SEVERITY_NOTIFICATION
0x9146 - GL_DEBUG_SEVERITY_HIGH
0x9147 - GL_DEBUG_SEVERITY_MEDIUM
0x9148 - GL_DEBUG_SEVERITY_LOW
```

## OSRT Event Class Values

OS runtime libraries can be traced to gather information about low-level userspace APIs. This traces the system call wrappers and thread synchronization interfaces exposed by the C runtime and POSIX Threads (pthread) libraries. This does not perform a complete runtime library API trace, but instead focuses on the functions that can take a long time to execute, or could potentially cause your thread be unscheduled from the CPU while waiting for an event to complete.

OSRT events may have callchains attached to them, depending on selected profiling settings. In such cases, one can use `callchainId` column to select relevant callchains from `OSRT_CALLCHAINS` table

### OSRT event class values

```
27 - TRACE_PROCESS_EVENT_OS_RUNTIME
31 - TRACE_PROCESS_EVENT_OS_RUNTIME_START
32 - TRACE_PROCESS_EVENT_OS_RUNTIME_FINISH
```

## DX12 Event Class Values

```
41 - TRACE_PROCESS_EVENT_DX12_API
42 - TRACE_PROCESS_EVENT_DX12_WORKLOAD
43 - TRACE_PROCESS_EVENT_DX12_START
44 - TRACE_PROCESS_EVENT_DX12_FINISH
52 - TRACE_PROCESS_EVENT_DX12_DISPLAY
59 - TRACE_PROCESS_EVENT_DX12_CREATE_OBJECT
```

## PIX Event Class Values

```
65 - TRACE_PROCESS_EVENT_DX12_DEBUG_API
75 - TRACE_PROCESS_EVENT_DX11_DEBUG_API
```

## Vulkan Event Class Values

```
53 - TRACE_PROCESS_EVENT_VULKAN_API
54 - TRACE_PROCESS_EVENT_VULKAN_WORKLOAD
55 - TRACE_PROCESS_EVENT_VULKAN_START
56 - TRACE_PROCESS_EVENT_VULKAN_FINISH
60 - TRACE_PROCESS_EVENT_VULKAN_CREATE_OBJECT
66 - TRACE_PROCESS_EVENT_VULKAN_DEBUG_API
```

## Vulkan Flags

```
VALID_BIT = 0x00000001
CACHE_HIT_BIT = 0x00000002
BASE_PIPELINE_ACCELERATION_BIT = 0x00000004
```

## SLI Event Class Values

```
62 - TRACE_PROCESS_EVENT_SLI
63 - TRACE_PROCESS_EVENT_SLI_START
64 - TRACE_PROCESS_EVENT_SLI_FINISH
```

## SLI Transfer Info Values

```
0 - P2P_SKIPPED
1 - P2P_EARLY_PUSH
2 - P2P_PUSH_FAILED
3 - P2P_2WAY_OR_PULL
4 - P2P_PRESENT
5 - P2P_DX12_INIT_PUSH_ON_WRITE
```

## WDDM Event Values

## VIDMM operation type values

```

0 - None
101 - RestoreSegments
102 - PurgeSegments
103 - CleanupPrimary
104 - AllocatePagingBufferResources
105 - FreePagingBufferResources
106 - ReportVidMmState
107 - RunApertureCoherencyTest
108 - RunUnmapToDummyPageTest
109 - DeferredCommand
110 - SuspendMemorySegmentAccess
111 - ResumeMemorySegmentAccess
112 - EvictAndFlush
113 - CommitVirtualAddressRange
114 - UncommitVirtualAddressRange
115 - DestroyVirtualAddressAllocator
116 - PageInDevice
117 - MapContextAllocation
118 - InitPagingProcessVaSpace
200 - CloseAllocation
202 - ComplexLock
203 - PinAllocation
204 - FlushPendingGpuAccess
205 - UnpinAllocation
206 - MakeResident
207 - Evict
208 - LockInAperture
209 - InitContextAllocation
210 - ReclaimAllocation
211 - DiscardAllocation
212 - SetAllocationPriority
1000 - EvictSystemMemoryOfferList

```

## Paging queue type values

```

0 - VIDMM_PAGING_QUEUE_TYPE_UMD
1 - VIDMM_PAGING_QUEUE_TYPE_Default
2 - VIDMM_PAGING_QUEUE_TYPE_Evict
3 - VIDMM_PAGING_QUEUE_TYPE_Reclaim

```

## Packet type values

```

0 - DXGKETW_RENDER_COMMAND_BUFFER
1 - DXGKETW_DEFERRED_COMMAND_BUFFER
2 - DXGKETW_SYSTEM_COMMAND_BUFFER
3 - DXGKETW_MMIOFLIP_COMMAND_BUFFER
4 - DXGKETW_WAIT_COMMAND_BUFFER
5 - DXGKETW_SIGNAL_COMMAND_BUFFER
6 - DXGKETW_DEVICE_COMMAND_BUFFER
7 - DXGKETW_SOFTWARE_COMMAND_BUFFER

```

## Engine type values

```
0 - DXGK_ENGINE_TYPE_OTHER
1 - DXGK_ENGINE_TYPE_3D
2 - DXGK_ENGINE_TYPE_VIDEO_DECODE
3 - DXGK_ENGINE_TYPE_VIDEO_ENCODE
4 - DXGK_ENGINE_TYPE_VIDEO_PROCESSING
5 - DXGK_ENGINE_TYPE_SCENE_ASSEMBLY
6 - DXGK_ENGINE_TYPE_COPY
7 - DXGK_ENGINE_TYPE_OVERLAY
8 - DXGK_ENGINE_TYPE_CRYPTO
```

## DMA interrupt type values

```
1 = DXGK_INTERRUPT_DMA_COMPLETED
2 = DXGK_INTERRUPT_DMA_PREEMPTED
4 = DXGK_INTERRUPT_DMA_FAULTED
9 = DXGK_INTERRUPT_DMA_PAGE_FAULTED
```

## Queue type values

```
0 = Queue_Packet
1 = Dma_Packet
2 = Paging_Queue_Packet
```

## Driver Events

### Load balance event type values

```
1 - LoadBalanceEvent_GPU
8 - LoadBalanceEvent_CPU
21 - LoadBalanceMasterEvent_GPU
22 - LoadBalanceMasterEvent_CPU
```

## OpenMP Events

### OpenMP event class values

```
78 - TRACE_PROCESS_EVENT_OPENMP
79 - TRACE_PROCESS_EVENT_OPENMP_START
80 - TRACE_PROCESS_EVENT_OPENMP_FINISH
```

## OpenMP event kind values

```

15 - OPENMP_EVENT_KIND_TASK_CREATE
16 - OPENMP_EVENT_KIND_TASK_SCHEDULE
17 - OPENMP_EVENT_KIND_CANCEL
20 - OPENMP_EVENT_KIND_MUTEX_RELEASED
21 - OPENMP_EVENT_KIND_LOCK_INIT
22 - OPENMP_EVENT_KIND_LOCK_DESTROY
25 - OPENMP_EVENT_KIND_DISPATCH
26 - OPENMP_EVENT_KIND_FLUSH
27 - OPENMP_EVENT_KIND_THREAD
28 - OPENMP_EVENT_KIND_PARALLEL
29 - OPENMP_EVENT_KIND_SYNC_REGION_WAIT
30 - OPENMP_EVENT_KIND_SYNC_REGION
31 - OPENMP_EVENT_KIND_TASK
32 - OPENMP_EVENT_KIND_MASTER
33 - OPENMP_EVENT_KIND_REDUCTION
34 - OPENMP_EVENT_KIND_MUTEX_WAIT
35 - OPENMP_EVENT_KIND_CRITICAL_SECTION
36 - OPENMP_EVENT_KIND_WORKSHARE

```

## OpenMP thread type values

```

1 - OpenMP Initial Thread
2 - OpenMP Worker Thread
3 - OpenMP Internal Thread
4 - Unknown

```

## OpenMP sync region kind values

```

1 - Barrier
2 - Implicit barrier
3 - Explicit barrier
4 - Implementation-dependent barrier
5 - Taskwait
6 - Taskgroup

```

## OpenMP task kind values

```

1 - Initial task
2 - Implicit task
3 - Explicit task

```

## OpenMP prior task status values

```

1 - Task completed
2 - Task yielded to another task
3 - Task was cancelled
7 - Task was switched out for other reasons

```

### OpenMP mutex kind values

```
1 - Waiting for lock
2 - Testing lock
3 - Waiting for nested lock
4 - Testing nested lock
5 - Waiting for entering critical section region
6 - Waiting for entering atomic region
7 - Waiting for entering ordered region
```

### OpenMP critical section kind values

```
5 - Critical section region
6 - Atomic region
7 - Ordered region
```

### OpenMP workshare kind values

```
1 - Loop region
2 - Sections region
3 - Single region (executor)
4 - Single region (waiting)
5 - Workshare region
6 - Distribute region
7 - Taskloop region
```

### OpenMP dispatch kind values

```
1 - Iteration
2 - Section
```

## 3.3. Common SQLite Examples

### Common Helper Commands

When utilizing sqlite3 command line tool, it's helpful to have data printed as named columns, this can be done with:

```
.mode column
.headers on
```

Default column width is determined by the data in the first row of results. If this doesn't work out well, you can specify widths manually.

```
.width 10 20 50
```

### Obtaining Sample Report

CLI interface of Nsight Systems was used to profile radixSortThrust CUDA sample, then the resulting .nsys-rep file was exported using the nsys export.

```
nsys profile --trace=cuda,osrt radixSortThrust
nsys export --type sqlite report1.nsys-rep
```

## Serialized Process and Thread Identifiers

Nsight Systems stores identifiers where events originated in serialized form. For events that have globalTid or globalPid fields exported, use the following code to extract numeric TID and PID.

```
SELECT globalTid / 0x1000000 % 0x1000000 AS PID, globalTid % 0x1000000 AS TID
FROM TABLE_NAME;
```

Note: globalTid field includes both TID and PID values, while globalPid only contains the PID value.

## Correlate CUDA Kernel Launches With CUDA API Kernel Launches

```
ALTER TABLE CUPTI_ACTIVITY_KIND_RUNTIME ADD COLUMN name TEXT;
ALTER TABLE CUPTI_ACTIVITY_KIND_RUNTIME ADD COLUMN kernelName TEXT;

UPDATE CUPTI_ACTIVITY_KIND_RUNTIME SET kernelName =
  (SELECT value FROM StringIds
   JOIN CUPTI_ACTIVITY_KIND_KERNEL AS cuda_gpu
     ON cuda_gpu.shortName = StringIds.id
    AND CUPTI_ACTIVITY_KIND_RUNTIME.correlationId = cuda_gpu.correlationId);

UPDATE CUPTI_ACTIVITY_KIND_RUNTIME SET name =
  (SELECT value FROM StringIds WHERE nameId = StringIds.id);
```

Select 10 longest CUDA API ranges that resulted in kernel execution.

```
SELECT name, kernelName, start, end FROM CUPTI_ACTIVITY_KIND_RUNTIME
WHERE kernelName IS NOT NULL ORDER BY end - start LIMIT 10;
```

Results:

name	kernelName	start	end
-----	-----	-----	-----
cudaLaunchKernel_v7000	RadixSortScanBinsKernel	658863435	658868490
cudaLaunchKernel_v7000	RadixSortScanBinsKernel	609755015	609760075
cudaLaunchKernel_v7000	RadixSortScanBinsKernel	632683286	632688349
cudaLaunchKernel_v7000	RadixSortScanBinsKernel	606495356	606500439
cudaLaunchKernel_v7000	RadixSortScanBinsKernel	603114486	603119586
cudaLaunchKernel_v7000	RadixSortScanBinsKernel	802729785	802734906
cudaLaunchKernel_v7000	RadixSortScanBinsKernel	593381170	593386294
cudaLaunchKernel_v7000	RadixSortScanBinsKernel	658759955	658765090
cudaLaunchKernel_v7000	RadixSortScanBinsKernel	681549917	681555059
cudaLaunchKernel_v7000	RadixSortScanBinsKernel	717812527	717817671

## Remove Ranges Overlapping With Overhead

Use the this query to count CUDA API ranges overlapping with the overhead ones.

Replace "SELECT COUNT(\*)" with "DELETE" to remove such ranges.

```
SELECT COUNT(*) FROM CUPTI_ACTIVITY_KIND_RUNTIME WHERE rowid IN
(
  SELECT cuda.rowid
  FROM PROFILER_OVERHEAD as overhead
  INNER JOIN CUPTI_ACTIVITY_KIND_RUNTIME as cuda ON
  (cuda.start BETWEEN overhead.start and overhead.end)
  OR (cuda.end BETWEEN overhead.start and overhead.end)
  OR (cuda.start < overhead.start AND cuda.end > overhead.end)
);
```

Results:

```
COUNT(*)
-----
1095
```

**Find CUDA API Calls That Resulted in Original Graph Node Creation.**

```
SELECT graph.graphNodeId, api.start, graph.start as graphStart, api.end,
       api.globalTid, api.correlationId, api.globalTid,
       (SELECT value FROM StringIds where api.nameId == id) as name
FROM CUPTI_ACTIVITY_KIND_RUNTIME as api
JOIN
  (
    SELECT start, graphNodeId, globalTid from CUDA_GRAPH_EVENTS
    GROUP BY graphNodeId
    HAVING COUNT(originalGraphNodeId) = 0
  ) as graph
ON api.globalTid == graph.globalTid AND api.start < graph.start AND api.end >
graph.start
ORDER BY graphNodeId;
```

## Results:

graphNodeId globalTid	start name	graphStart	end	globalTid	correlationId
1	584366518	584378040	584379102	281560221750233	109
2	584379402	584382428	584383139	281560221750233	110
3	584390663	584395352	584396053	281560221750233	111
4	584396314	584397857	584398438	281560221750233	112
5	584398759	584400311	584400812	281560221750233	113
6	584401083	584403047	584403527	281560221750233	114
7	584403928	584404920	584405491	281560221750233	115
29	632107852	632117921	632121407	281560221750233	144
30	632122168	632125545	632127989	281560221750233	145
31	632131546	632133339	632135584	281560221750233	147
34	632162514	632167393	632169297	281560221750233	151
35	632170068	632173334	632175388	281560221750233	152

## Backtraces for OSRT Ranges

Adding text columns makes results of the query below more human-readable.

```
ALTER TABLE OSRT_API ADD COLUMN name TEXT;
UPDATE OSRT_API SET name = (SELECT value FROM StringIds WHERE OSRT_API.nameId = StringIds.id);

ALTER TABLE OSRT_CALLCHAINS ADD COLUMN symbolName TEXT;
UPDATE OSRT_CALLCHAINS SET symbolName = (SELECT value FROM StringIds WHERE symbol = StringIds.id);

ALTER TABLE OSRT_CALLCHAINS ADD COLUMN moduleName TEXT;
UPDATE OSRT_CALLCHAINS SET moduleName = (SELECT value FROM StringIds WHERE module = StringIds.id);
```

## Print backtrace of the longest OSRT range

```
SELECT globalTid / 0x1000000 % 0x1000000 AS PID, globalTid % 0x1000000 AS TID,
       start, end, name, callchainId, stackDepth, symbolName, moduleName
FROM OSRT_API LEFT JOIN OSRT_CALLCHAINS ON callchainId == OSRT_CALLCHAINS.id
WHERE OSRT_API.rowid IN (SELECT rowid FROM OSRT_API ORDER BY end - start DESC
LIMIT 1)
ORDER BY stackDepth LIMIT 10;
```

**Results:**

PID	TID	start	end	name	moduleName
callchainId	stackDepth	symbolName			
-----					
-----					
19163	19176	360897690	860966851	pthread_cond_timedwait	88
	0	pthread_cond_timedwait@GLIBC_2		/lib/x86_64-linux-gnu/	
libpthread-2.27.so					
19163	19176	360897690	860966851	pthread_cond_timedwait	88
	1	0x7fbc983b7227		/usr/lib/x86_64-linux-gnu/	
libcuda.so.418					
19163	19176	360897690	860966851	pthread_cond_timedwait	88
	2	0x7fbc9835d5c7		/usr/lib/x86_64-linux-gnu/	
libcuda.so.418					
19163	19176	360897690	860966851	pthread_cond_timedwait	88
	3	0x7fbc983b64a8		/usr/lib/x86_64-linux-gnu/	
libcuda.so.418					
19163	19176	360897690	860966851	pthread_cond_timedwait	88
	4	start_thread		/lib/x86_64-linux-gnu/	
libpthread-2.27.so					
19163	19176	360897690	860966851	pthread_cond_timedwait	88
	5	__clone		/lib/x86_64-linux-gnu/	
libc-2.27.so					

**Profiled processes output streams**

```
ALTER TABLE ProcessStreams ADD COLUMN filename TEXT;
UPDATE ProcessStreams SET filename = (SELECT value FROM StringIds WHERE
  ProcessStreams.filenameId = StringIds.id);

ALTER TABLE ProcessStreams ADD COLUMN content TEXT;
UPDATE ProcessStreams SET content = (SELECT value FROM StringIds WHERE
  ProcessStreams.contentId = StringIds.id);
```

**Select all collected stdout and stderr streams.**

```
select globalPid / 0x1000000 % 0x1000000 AS PID, filename, content from
  ProcessStreams;
```

**Results:**

PID	filename	content
-----		
19163	/tmp/nvidia/nsight_systems/streams/pid_19163_stdout.log	/home/user_name/NVIDIA_CUDA-10.1_Samples/6_Advanced/radixSortThrust/radixSortThrust Starting...
		GPU Device 0: "Quadro P2000" with compute capability 6.1
		Sorting 1048576 32-bit unsigned int keys and values
		radixSortThrust, Throughput = 401.0872 MElements/s, Time = 0.00261 s, Size = 1048576 elements
		Test passed
19163	/tmp/nvidia/nsight_systems/streams/pid_19163_stderr.log	

**Thread Summary**

Please note, that Nsight Systems applies additional logic during sampling events processing to work around lost events. This means that the results of the below query might differ slightly from the ones shown in “Analysis summary” tab.

Thread summary calculated using CPU cycles (when available).

```

SELECT
  globalTid / 0x1000000 % 0x1000000 AS PID,
  globalTid % 0x1000000 AS TID,
  ROUND(100.0 * SUM(cpuCycles) /
    (
      SELECT SUM(cpuCycles) FROM COMPOSITE_EVENTS
      GROUP BY globalTid / 0x100000000000000 % 0x100
    ),
    2
  ) as CPU_utilization,
  (SELECT value FROM StringIds WHERE id =
    (
      SELECT nameId FROM ThreadNames
      WHERE ThreadNames.globalTid = COMPOSITE_EVENTS.globalTid
    )
  ) as thread name
FROM COMPOSITE_EVENTS
GROUP BY globalTid
ORDER BY CPU_utilization DESC
LIMIT 10;

```

**Results:**

PID	TID	CPU_utilization	thread_name
-----	-----	-----	-----
19163	19163	98.4	radixSortThrust
19163	19168	1.35	CUPTI worker th
19163	19166	0.25	[NS]

Thread running time may be calculated using scheduling data, when PMU counter data was not collected.

```
CREATE INDEX sched_start ON SCHED_EVENTS (start);

CREATE TABLE CPU_USAGE AS
SELECT
    first.globalTid as globalTid,
    (SELECT nameId FROM ThreadNames WHERE ThreadNames.globalTid =
    first.globalTid) as nameId,
    sum(second.start - first.start) as total_duration,
    count() as ranges_count
FROM SCHED_EVENTS as first
LEFT JOIN SCHED_EVENTS as second
ON second.rowid =
    (
        SELECT rowid
        FROM SCHED_EVENTS
        WHERE start > first.start AND globalTid = first.globalTid
        ORDER BY start ASC
        LIMIT 1
    )
WHERE first.isSchedIn != 0
GROUP BY first.globalTid
ORDER BY total_duration DESC;

SELECT
    globalTid / 0x1000000 % 0x1000000 AS PID,
    globalTid % 0x1000000 AS TID,
    (SELECT value FROM StringIds where nameId == id) as thread_name,
    ROUND(100.0 * total_duration / (SELECT SUM(total_duration) FROM CPU_USAGE),
    2) as CPU_utilization
FROM CPU_USAGE
ORDER BY CPU_utilization DESC;
```

**Results:**

PID	TID	thread_name	CPU_utilization
-----	-----	-----	-----
19163	19163	radixSortThrust	93.74
19163	19169	radixSortThrust	3.22
19163	19168	CUPTI worker th	2.46
19163	19166	[NS]	0.44
19163	19172	radixSortThrust	0.07
19163	19167	[NS Comms]	0.05
19163	19176	radixSortThrust	0.02
19163	19170	radixSortThrust	0.0

**Function Table**

These examples demonstrate how to calculate Flat and BottomUp (for top level only) views statistics.

To set up:

```
ALTER TABLE SAMPLING_CALLCHAINS ADD COLUMN symbolName TEXT;
UPDATE SAMPLING_CALLCHAINS SET symbolName = (SELECT value FROM StringIds WHERE
symbol = StringIds.id);

ALTER TABLE SAMPLING_CALLCHAINS ADD COLUMN moduleName TEXT;
UPDATE SAMPLING_CALLCHAINS SET moduleName = (SELECT value FROM StringIds WHERE
module = StringIds.id);
```

To get flat view:

```
SELECT symbolName, moduleName, ROUND(100.0 * sum(cpuCycles) /
(SELECT SUM(cpuCycles) FROM COMPOSITE_EVENTS), 2) AS flatTimePercentage
FROM SAMPLING_CALLCHAINS
LEFT JOIN COMPOSITE_EVENTS ON SAMPLING_CALLCHAINS.id == COMPOSITE_EVENTS.id
GROUP BY symbol, module
ORDER BY flatTimePercentage DESC
LIMIT 5;
```

To get BottomUp view (top level only):

```
SELECT symbolName, moduleName, ROUND(100.0 * sum(cpuCycles) /
(SELECT SUM(cpuCycles) FROM COMPOSITE_EVENTS), 2) AS selfTimePercentage
FROM SAMPLING_CALLCHAINS
LEFT JOIN COMPOSITE_EVENTS ON SAMPLING_CALLCHAINS.id == COMPOSITE_EVENTS.id
WHERE stackDepth == 0
GROUP BY symbol, module
ORDER BY selfTimePercentage DESC
LIMIT 5;
```

Results:

symbolName	moduleName	flatTimePercentage
[Max depth]	[Max depth]	99.92
thrust::zip	/home/user_	24.17
thrust::zip	/home/user_	24.17
thrust::det	/home/user_	24.17
thrust::det	/home/user_	24.17

symbolName	moduleName	selfTimePercentage
0x7fbc984982b6	/usr/lib/x86_64-linux-gnu/libcuda.so.418.39	5.29
0x7fbc982d0010	/usr/lib/x86_64-linux-gnu/libcuda.so.418.39	2.81
thrust::iterat	/home/user_name/NVIDIA_CUDA-10.1_Samples/6_	2.23
thrust::iterat	/home/user_name/NVIDIA_CUDA-10.1_Samples/6_	1.55
void thrust::i	/home/user_name/NVIDIA_CUDA-10.1_Samples/6_	1.55

## DX12 API Frame Duration Histogram

The example demonstrates how to calculate DX12 CPU frames duration and construct a histogram out of it.

```
CREATE INDEX DX12_API_ENDTS ON DX12_API (end);

CREATE TEMP VIEW DX12_API_FPS AS SELECT end AS start,
    (SELECT end FROM DX12_API
     WHERE end > outer.end AND nameId == (SELECT id FROM StringIds
     WHERE value == "IDXGISwapChain::Present")
     ORDER BY end ASC LIMIT 1) AS end
FROM DX12_API AS outer
WHERE nameId == (SELECT id FROM StringIds WHERE value ==
"IDXGISwapChain::Present")
ORDER BY end;
```

Number of frames with a duration of [X, X + 1) milliseconds.

```
SELECT
    CAST((end - start) / 1000000.0 AS INT) AS duration_ms,
    count(*)
FROM DX12_API_FPS
WHERE end IS NOT NULL
GROUP BY duration_ms
ORDER BY duration_ms;
```

Results:

duration_ms	count(*)
-----	-----
3	1
4	2
5	7
6	153
7	19
8	116
9	16
10	8
11	2
12	2
13	1
14	4
16	3
17	2
18	1

## GPU Context Switch Events Enumeration

GPU context duration is between first BEGIN and a matching END event.

```
SELECT (CASE tag WHEN 8 THEN "BEGIN" WHEN 7 THEN "END" END) AS tag,
    globalPid / 0x1000000 % 0x1000000 AS PID,
    vmId, seqNo, contextId, timestamp, gpuId FROM FECS_EVENTS
WHERE tag in (7, 8) ORDER BY seqNo LIMIT 10;
```

**Results:**

tag	PID	vmId	seqNo	contextId	timestamp	gpuId
-----	-----	-----	-----	-----	-----	
BEGIN	23371	0	0	1048578	56759171	0
BEGIN	23371	0	1	1048578	56927765	0
BEGIN	23371	0	3	1048578	63799379	0
END	23371	0	4	1048578	63918806	0
BEGIN	19397	0	5	1048577	64014692	0
BEGIN	19397	0	6	1048577	64250369	0
BEGIN	19397	0	8	1048577	1918310004	0
END	19397	0	9	1048577	1918521098	0
BEGIN	19397	0	10	1048577	2024164744	0
BEGIN	19397	0	11	1048577	2024358650	0

**Resolve NVTX Category Name**

The example demonstrates how to resolve NVTX category name for NVTX marks and ranges.

```

WITH
  event AS (
    SELECT *
    FROM NVTX_EVENTS
    WHERE eventType IN (34, 59, 60) -- mark, push/pop, start/end
  ),
  category AS (
    SELECT
      category,
      domainId,
      text AS categoryName
    FROM NVTX_EVENTS
    WHERE eventType == 33 -- new category
  )
SELECT
  start,
  end,
  globalTid,
  eventType,
  domainId,
  category,
  categoryName,
  text
FROM event JOIN category USING (category, domainId)
ORDER BY start;

```

## Results:

start	end	globalTid	eventType	domainId	category
categoryName		text			
-----	-----	-----	-----	-----	-----
18281150	18311960	281534938484214	59	0	1
FirstCategoryUnderDefault		Push Pop Range A			
18288187	18306674	281534938484214	59	0	2
SecondCategoryUnderDefault		Push Pop Range B			
18294247		281534938484214	34	0	1
FirstCategoryUnderDefault		Mark A			
18300034		281534938484214	34	0	2
SecondCategoryUnderDefault		Mark B			
18345546	18372595	281534938484214	60	1	1
FirstCategoryUnderMyDomain		Start End Range			
18352924	18378342	281534938484214	60	1	2
SecondCategoryUnderMyDomain		Start End Range			
18359634		281534938484214	34	1	1
FirstCategoryUnderMyDomain		Mark A			
18365448		281534938484214	34	1	2
SecondCategoryUnderMyDomain		Mark B			

## Rename CUDA Kernels with NVTX

The example demonstrates how to map innermost NVTX push-pop range to a matching CUDA kernel run.

```
ALTER TABLE CUPTI_ACTIVITY_KIND_KERNEL ADD COLUMN nvtxRange TEXT;
CREATE INDEX nvtx_start ON NVTX_EVENTS (start);

UPDATE CUPTI_ACTIVITY_KIND_KERNEL SET nvtxRange = (
  SELECT NVTX_EVENTS.text
  FROM NVTX_EVENTS JOIN CUPTI_ACTIVITY_KIND_RUNTIME ON
    NVTX_EVENTS.eventType == 59 AND
    NVTX_EVENTS.globalTid == CUPTI_ACTIVITY_KIND_RUNTIME.globalTid AND
    NVTX_EVENTS.start <= CUPTI_ACTIVITY_KIND_RUNTIME.start AND
    NVTX_EVENTS.end >= CUPTI_ACTIVITY_KIND_RUNTIME.end
  WHERE
    CUPTI_ACTIVITY_KIND_KERNEL.correlationId ==
    CUPTI_ACTIVITY_KIND_RUNTIME.correlationId
  ORDER BY NVTX_EVENTS.start DESC LIMIT 1
);

SELECT start, end, globalPid, StringIds.value as shortName, nvtxRange
FROM CUPTI_ACTIVITY_KIND_KERNEL JOIN StringIds ON shortName == id
ORDER BY start LIMIT 6;
```

## Results:

start	end	globalPid	shortName	nvtxRange
-----	-----	-----	-----	-----
526545376	526676256	72057700439031808	MatrixMulCUDA	
526899648	527030368	72057700439031808	MatrixMulCUDA	Add
527031648	527162272	72057700439031808	MatrixMulCUDA	Add
527163584	527294176	72057700439031808	MatrixMulCUDA	My Kernel
527296160	527426592	72057700439031808	MatrixMulCUDA	My Range
527428096	527558656	72057700439031808	MatrixMulCUDA	

## Select CUDA Calls With Backtraces

```
ALTER TABLE CUPTI_ACTIVITY_KIND_RUNTIME ADD COLUMN name TEXT;
UPDATE CUPTI_ACTIVITY_KIND_RUNTIME SET name = (SELECT value FROM StringIds WHERE
CUPTI_ACTIVITY_KIND_RUNTIME.nameId = StringIds.id);

ALTER TABLE CUDA_CALLCHAINS ADD COLUMN symbolName TEXT;
UPDATE CUDA_CALLCHAINS SET symbolName = (SELECT value FROM StringIds WHERE
symbol = StringIds.id);

SELECT globalTid % 0x1000000 AS TID,
       start, end, name, callchainId, stackDepth, symbolName
FROM CUDA_CALLCHAINS JOIN CUPTI_ACTIVITY_KIND_RUNTIME ON callchainId ==
CUDA_CALLCHAINS.id
ORDER BY callchainId, stackDepth LIMIT 11;
```

### Results:

TID	start	end	name	callchainId	stackDepth	
symbolName						
-----	-----	-----	-----	-----	-----	
11928	168976467	169077826	cuMemAlloc_v2	1	0	
0x7f13c44f02ab						
11928	168976467	169077826	cuMemAlloc_v2	1	1	
0x7f13c44f0b8f						
11928	168976467	169077826	cuMemAlloc_v2	1	2	
0x7f13c44f3719						
11928	168976467	169077826	cuMemAlloc_v2	1	3	
cuMemAlloc_v2						
11928	168976467	169077826	cuMemAlloc_v2	1	4	
cuda::driver						
11928	168976467	169077826	cuMemAlloc_v2	1	5	
cuda::cudaAp						
11928	168976467	169077826	cuMemAlloc_v2	1	6	
cudaMalloc						
11928	168976467	169077826	cuMemAlloc_v2	1	7	
cudaError cuda						
11928	168976467	169077826	cuMemAlloc_v2	1	8	main
11928	168976467	169077826	cuMemAlloc_v2	1	9	
__libc_start_m						
11928	168976467	169077826	cuMemAlloc_v2	1	10	
_start						

## SLI Peer-to-Peer Query

The example demonstrates how to query SLI Peer-to-Peer events with resource size greater than value and within a time range sorted by resource size descending.

```
SELECT *
FROM SLI_P2P
WHERE resourceSize < 98304 AND start > 1568063100 AND end < 1579468901
ORDER BY resourceSize DESC;
```

## Results:

start	end	eventClass	globalTid	gpu	frameId	
transferSkipped	srcGpu	dstGpu	numSubResources	resourceSize		
subResourceIdx	smplWidth	smplHeight	smplDepth	bytesPerElement		
dxgiFormat	logSurfaceNames	transferInfo	isEarlyPushManagedByNvApi			
useAsyncP2pForResolve	transferFuncName	regimeName	debugName	bindType		
-----	-----	-----	-----	-----	-----	-----
-----	-----	-----	-----	-----	-----	-----
-----	-----	-----	-----	-----	-----	-----
1570351100	1570351101	62	72057698056667136	0	771	0
	256	512	1	1048576	0	
256	256	1	16	2		
3	0		0			
1570379300	1570379301	62	72057698056667136	0	771	0
	256	512	1	1048576	0	
64	64	64	4	31		
3	0		0			
1572316400	1572316401	62	72057698056667136	0	773	0
	256	512	1	1048576	0	
256	256	1	16	2		
3	0		0			
1572345400	1572345401	62	72057698056667136	0	773	0
	256	512	1	1048576	0	
64	64	64	4	31		
3	0		0			
1574734300	1574734301	62	72057698056667136	0	775	0
	256	512	1	1048576	0	
256	256	1	16	2		
3	0		0			
1574767200	1574767201	62	72057698056667136	0	775	0
	256	512	1	1048576	0	
64	64	64	4	31		
3	0		0			

## Generic Events

## Syscall usage histogram by PID:

```

SELECT json_extract(data, '$.common_pid') AS PID, count(*) AS total
FROM GENERIC_EVENTS WHERE PID IS NOT NULL AND typeId = (
  SELECT typeId FROM GENERIC_EVENT_TYPES
  WHERE json_extract(data, '$.Name') = "raw_syscalls:sys_enter")
GROUP BY PID
ORDER BY total DESC
LIMIT 10;

```

Results:

PID	total
-----	-----
5551	32811
9680	3988
4328	1477
9564	1246
4376	1204
4377	1167
4357	656
4355	655
4356	640
4354	633

### Fetching Generic Events in JSON Format

Text and JSON export modes don't include generic events. Use the below queries (without LIMIT clause) to extract JSON lines representation of generic events, types and sources.

```
SELECT json_insert('{}',
  '$.sourceId', sourceId,
  '$.data', json(data)
)
FROM GENERIC_EVENT_SOURCES LIMIT 2;

SELECT json_insert('{}',
  '$.typeId', typeId,
  '$.sourceId', sourceId,
  '$.data', json(data)
)
FROM GENERIC_EVENT_TYPES LIMIT 2;

SELECT json_insert('{}',
  '$.rawTimestamp', rawTimestamp,
  '$.timestamp', timestamp,
  '$.typeId', typeId,
  '$.data', json(data)
)
FROM GENERIC_EVENTS LIMIT 2;
```

## Results:

```

json_insert('{}',
  '$.sourceId', sourceId,
  '$.data', json(data)
)

-----

{"sourceId":72057602627862528,"data":
{"Name":"FTrace","TimeSource":"ClockMonotonicRaw","SourceGroup":"FTrace"}}
json_insert('{}',
  '$.typeId', typeId,
  '$.sourceId', sourceId,
  '$.data', json(data)
)

-----

{"typeId":72057602627862547,"sourceId":72057602627862528,"data":
{"Name":"raw_syscalls:sys_enter","Format":"\NR %ld (%lx,
 %lx, %lx, %lx, %lx, %lx)\", REC->id, REC->args[0], REC-
>args[1], REC->args[2], REC->args[3], REC->args[4], REC-
>args[5]","Fields":[{"Name":"common_pid","Prefix":"int","Suffix":""},
{"Name":"id","Prefix":"long","S
{"typeId":72057602627862670,"sourceId":72057602627862528,"data":
{"Name":"irq:irq_handler_entry","Format":"\ irq=%d name=%s\", REC->irq,
__get_str(name)","Fields":[{"Name":"common_pid","Prefix":"int","Suffix":""},
{"Name":"irq","Prefix":"int","Suffix":""}, {"Name":"name","Prefix":"__data_loc
char[]","Suffix":""}, {"Name":"common_type",
json_insert('{}',
  '$.rawTimestamp', rawTimestamp,
  '$.timestamp', timestamp,
  '$.typeId', typeId,
  '$.data', json(data)
)

-----

{"rawTimestamp":1183694330725221,"timestamp":6236683,"typeId":72057602627862670,"data":
{"common_pid":"0","irq":"66","name":"327696","common_type":"142","common_flags":"9","common_p
{"rawTimestamp":1183694333695687,"timestamp":9207149,"typeId":72057602627862670,"data":
{"common_pid":"0","irq":"66","name":"327696","common_type":"142","common_flags":"9","common_p

```

### 3.4. Arrow Format Description

The Arrow type exported file uses the IPC stream format to store the data in a file. The produced file comprises only the tables that contain data, meaning that depending on the profiled applications, some tables might not appear in the output file. The tables can be read by opening the file as an arrow stream. For example one can use the **open\_stream** function from the arrow python package. For more information one can refer to the Apache Arrow documentation [1, 2].

The name of each table is included in the schema metadata. Thus, while reading each table, the user can extract the table title from the metadata. The table name metadata

field has the key **table\_name**. The titles of all the available tables can be found in section [SQLite Schema Reference](#).

## 3.5. JSON and Text Format Description

JSON and TXT export formats are generated by serializing buffered messages, each on a new line. First, all collected events are processed. Then strings are serialized, followed by stdout, stderr streams if any, followed by thread names.

Output layout:

```
{Event #1}
{Event #2}
...
{Event #N}
{Strings}
{Streams}
{Threads}
```

For easier grepping of JSON output, the **--separate-strings** switch may be used to force manual splitting of strings, streams and thread names data.

Example line split: **nsys export --export-json --separate-strings sample.nsys-rep -- -**

```
{"type":"String","id":"3720","value":"Process 14944 was launched by the
profiler"}
{"type":"String","id":"3721","value":"Profiling has started."}
{"type":"String","id":"3722","value":"Profiler attached to the process."}
{"type":"String","id":"3723","value":"Profiling has stopped."}
{"type":"ThreadName","globalTid":"72057844756653436","nameId":"14","priority":"10"}
{"type":"ThreadName","globalTid":"72057844756657940","nameId":"15","priority":"10"}
{"type":"ThreadName","globalTid":"72057844756654400","nameId":"24","priority":"10"}
```

Compare with: **nsys export --export-json sample.nsys-rep -- -**

```
{"data":["[Unknown]","[Unknown kernel module]","[Max depth]","[Broken
backtraces]",
"[Called from
Java]","QnxKernelTrace","mm","task_submit","class_id","syncpt_id",
"syncpt_thresh","pid","tid","FTrace","[NSys]","[NSys Comms]","..." ,"Process
14944 was launched by the profiler","Profiling has started.","Profiler
attached
to the process.","Profiling has stopped."]}
{"data":[{"nameIdx":"14","priority":"10","globalTid":"72057844756653436"},
{"nameIdx":"15","priority":"10","globalTid":"72057844756657940"},
{"nameIdx":"24",
"priority":"10","globalTid":"72057844756654400"}]}
```

Note, that only last few lines are shown here for clarity and that carriage returns and indents were added to avoid wrapping documentation.

# Chapter 4.

## REPORT SCRIPTS

### Report Scripts Shipped With Nsight Systems

The Nsight Systems development team created and maintains a set of report scripts for some of the commonly requested reports. These scripts will be updated to adapt to any changes in SQLite schema or internal data structures.

These scripts are located in the Nsight Systems package in the Target-<architecture>/reports directory. The following standard reports are available:

#### apigpusum[:base] -- CUDA API & GPU Summary (CUDA API + kernels + memory ops)

##### Arguments

- ▶ **base** - Optional argument, if given, will cause summary to be over the base name of the kernel, rather than the templated name.

Output: All time values given in nanoseconds

- ▶ **Time(%)** : Percentage of **Total Time**
- ▶ **Total Time** : The total time used by all executions of this kernel
- ▶ **Instances**: The number of executions of this object
- ▶ **Average** : The average execution time of this kernel
- ▶ **Minimum** : The smallest execution time of this kernel
- ▶ **Maximum** : The largest execution time of this kernel
- ▶ **Category** : The category of the operation
- ▶ **Operation** : The name of the kernel

This report provides a summary of CUDA API calls, kernels and memory operations, and their execution times. Note that the **Time(%)** column is calculated using a summation of the **Total Time** column, and represents that API call's, kernel's, or memory operation's percent of the execution time of the APIs, kernels and memory operations listed, and not a percentage of the application wall or CPU execution time.

This report combines data from the `cudaapisum`, `gpukernsum`, and `gpumemsum` reports. It is very similar to profile section of `nvprof --dependency-analysis`.

## cudaapisum -- CUDA API Summary

Arguments - None

Output: All time values given in nanoseconds

- ▶ **Time(%)** : Percentage of **Total Time**
- ▶ **Total Time** : The total time used by all executions of this function
- ▶ **Num Calls** : The number of calls to this function
- ▶ **Average** : The average execution time of this function
- ▶ **Minimum** : The smallest execution time of this function
- ▶ **Maximum** : The largest execution time of this function
- ▶ **Name** : The name of the function

This report provides a summary of CUDA API functions and their execution times. Note that the **Time(%)** column is calculated using a summation of the **Total Time** column, and represents that function's percent of the execution time of the functions listed, and not a percentage of the application wall or CPU execution time.

## cudaapitrace -- CUDA API Trace

Arguments - None

Output: All time values given in nanoseconds

- ▶ **Start** : Timestamp when API call was made
- ▶ **Duration** : Length of API calls
- ▶ **Name** : API function name
- ▶ **Result** : return value of API call
- ▶ **CorrID** : Correlation used to map to other CUDA calls
- ▶ **Pid** : Process ID that made the call
- ▶ **Tid** : Thread ID that made the call
- ▶ **T-Pri** : Run priority of call thread
- ▶ **Thread Name** : Name of thread that called API function

This report provides a trace record of CUDA API function calls and their execution times.

## gpukernsum[:base] -- CUDA GPU Kernel Summary

Arguments

- ▶ **base** - Optional argument, if given, will cause summary to be over the base name of the kernel, rather than the templated name.

Output: All time values given in nanoseconds

- ▶ **Time(%)** : Percentage of **Total Time**

- ▶ **Total Time** : The total time used by all executions of this kernel
- ▶ **Instances** : The number of calls to this kernel
- ▶ **Average** : The average execution time of this kernel
- ▶ **Minimum** : The smallest execution time of this kernel
- ▶ **Maximum** : The largest execution time of this kernel
- ▶ **Name** : The name of the kernel

This report provides a summary of CUDA kernels and their execution times. Note that the **Time(%)** column is calculated using a summation of the **Total Time** column, and represents that kernel's percent of the execution time of the kernels listed, and not a percentage of the application wall or CPU execution time.

## gpumemsize -- GPU Memory Operations Summary (by Size)

Arguments - None

Output: All memory values given in KiB

- ▶ **Total** : Total number of KiB utilized by this operation
- ▶ **Operations** : Number of executions of this operation
- ▶ **Average** : The average memory size of this operation
- ▶ **Minimum** : The smallest memory size of this operation
- ▶ **Maximum** : The largest memory size of this operation
- ▶ **Name** : The name of the operation

This report provides a summary of GPU memory operations and the amount of memory they utilize.

## gpumemtimesum -- GPU Memory Operations Summary (by Time)

Arguments - None

Output: All memory values given in KiB

- ▶ **Time(%)** : Percentage of **Total Time**
- ▶ **Total Time** : The total time used by all executions of this operation
- ▶ **Operations** : The number of operations of this type
- ▶ **Average** : The average execution time of this operation
- ▶ **Minimum** : The smallest execution time of this operation
- ▶ **Maximum** : The largest execution time of this operation
- ▶ **Operation** : The name of the memory operation

This report provides a summary of GPU memory operations and their execution times. Note that the **Time(%)** column is calculated using a summation of the **Total Time** column, and represents that operation's percent of the execution time of the operations listed, and not a percentage of the application wall or CPU execution time.

## gpusum[:base] -- GPU Summary (kernels + memory operations)

### Arguments

- ▶ **base** - Optional argument, if given, will cause summary to be over the base name of the kernel, rather than the templated name.

Output: All time values given in nanoseconds

- ▶ **Time(%)** : Percentage of **Total Time**
- ▶ **Total Time** : The total time used by all executions of this kernel
- ▶ **Instances** : The number of executions of this object
- ▶ **Average** : The average execution time of this kernel
- ▶ **Minimum** : The smallest execution time of this kernel
- ▶ **Maximum** : The largest execution time of this kernel
- ▶ **Category** : The category of the operation
- ▶ **Name** : The name of the kernel

This report provides a summary of CUDA kernels and memory operations, and their execution times. Note that the **Time(%)** column is calculated using a summation of the **Total Time** column, and represents that kernel's or memory operation's percent of the execution time of the kernels and memory operations listed, and not a \ percentage of the application wall or CPU execution time.

This report combines data from the **gpukernsum** and **gpumentimesum** reports. This report is very similar to output of the command **nvprof --print-gpu-summary**.

## gputrace -- CUDA GPU Trace

### Arguments - None

Output:

- ▶ **Start** : Start time of trace event in seconds
- ▶ **Duration** : Length of event in nanoseconds
- ▶ **CorrId** : Correlation ID
- ▶ **GrdX, GrdY, GrdZ** : Grid values
- ▶ **BlkX, BlkY, BlkZ** : Block values
- ▶ **Reg/Trd** : Registers per thread
- ▶ **StcSMem** : Size of Static Shared Memory
- ▶ **DymSMem** : Size of Dynamic Shared Memory
- ▶ **Bytes** : Size of memory operation
- ▶ **Thru** : Throughput in MB per Second
- ▶ **SrcMemKd** : Malloc source memory kind or memset memory kind
- ▶ **DstMemKd** : Malloc destination memory kind
- ▶ **Device** : GPU device name and ID
- ▶ **Ctx** : Context ID

- ▶ **Strm** : Stream ID
- ▶ **Name** : Trace event name

This report displays a trace of CUDA kernels and memory operations. Items are sorted by start time.

## nvtxppsum -- NVTX Push/Pop Range Summary

Arguments - None

Output: All time values given in nanoseconds

- ▶ **Time(%)** : Percentage of **Total Time**
- ▶ **Total Time** : The total time used by all instances of this range
- ▶ **Instances** : The number of instances of this range
- ▶ **Average** : The average execution time of this range
- ▶ **Minimum** : The smallest execution time of this range
- ▶ **Maximum** : The largest execution time of this range
- ▶ **Range** : The name of the range

This report provides a summary of NV Tools Extensions Push/Pop Ranges and their execution times. Note that the **Time(%)** column is calculated using a summation of the **Total Time** column, and represents that range's percent of the execution time of the ranges listed, and not a percentage of the application wall or CPU execution time.

## openmpevtsum -- OpenMP Event Summary

Arguments - None

Output: All time values given in nanoseconds

- ▶ **Time(%)** : Percentage of **Total Time**
- ▶ **Total Time** : The total time used by all executions of event type
- ▶ **Count** : The number of event type
- ▶ **Average** : The average execution time of event type
- ▶ **Minimum** : The smallest execution time of event type
- ▶ **Maximum** : The largest execution time of event type
- ▶ **Name** : The name of the event

This report provides a summary of OpenMP events and their execution times. Note that the **Time(%)** column is calculated using a summation of the **Total Time** column, and represents that event type's percent of the execution time of the events listed, and not a percentage of the application wall or CPU execution time.

## osrtsum -- OS Runtime Summary

Arguments - None

Output: All time values given in nanoseconds

- ▶ **Time(%)** : Percentage of **Total Time**

- ▶ **Total Time** : The total time used by all executions of this function
- ▶ **Num Calls** : The number of calls to this function
- ▶ **Average** : The average execution time of this function
- ▶ **Minimum** : The smallest execution time of this function
- ▶ **Maximum** : The largest execution time of this function
- ▶ **Name** : The name of the function

This report provides a summary of operating system functions and their execution times. Note that the **Time(%)** column is calculated using a summation of the **Total Time** column, and represents that function's percent of the execution time of the functions listed, and not a percentage of the application wall or CPU execution time.

## vulkanmarkerssum -- Vulkan Range Summary

Arguments - None

Output: All time values given in nanoseconds

- ▶ **Time(%)** : Percentage of **Total Time**
- ▶ **Total Time** : The total time used by all executions of this function
- ▶ **Instances** : The number of instances of this range
- ▶ **Average** : The average execution time of this function
- ▶ **Minimum** : The smallest execution time of this function
- ▶ **Maximum** : The largest execution time of this function
- ▶ **StdDev** : The standard deviation of execution time of this range
- ▶ **Range** : The name of the range

This report provides a summary of Vulkan debug markers on the CPU, and their execution times. Note that the **Time(%)** column is calculated using a summation of the **Total Time** column, and represents that function's percent of the execution time of the functions listed, and not a percentage of the application wall or CPU execution time.

## pixsum -- PIX Range Summary

Arguments - None

Output: All time values given in nanoseconds

- ▶ **Time(%)** : Percentage of **Total Time**
- ▶ **Total Time** : The total time used by all executions of this function
- ▶ **Instances** : The number of instances of this range
- ▶ **Average** : The average execution time of this function
- ▶ **Minimum** : The smallest execution time of this function
- ▶ **Maximum** : The largest execution time of this function
- ▶ **StdDev** : The standard deviation of execution time of this range
- ▶ **Range** : The name of the range

This report provides a summary of PIX CPU debug markers, and their execution times. Note that the **Time(%)** column is calculated using a summation of the **Total Time**

column, and represents that function's percent of the execution time of the functions listed, and not a percentage of the application wall or CPU execution time.

## khrdebugsum -- OpenGL KHR\_debug Range Summary

Arguments - None

Output: All time values given in nanoseconds

- ▶ **Time(%)** : Percentage of **Total Time**
- ▶ **Total Time** : The total time used by all executions of this function
- ▶ **Instances** : The number of instances of this range
- ▶ **Average** : The average execution time of this function
- ▶ **Minimum** : The smallest execution time of this function
- ▶ **Maximum** : The largest execution time of this function
- ▶ **StdDev** : The standard deviation of execution time of this range
- ▶ **Range** : The name of the range

This report provides a summary of OpenGL KHR\_debug CPU PUSH/POP debug Ranges, and their execution times. Note that the **Time(%)** column is calculated using a summation of the **Total Time** column, and represents that function's percent of the execution time of the functions listed, and not a percentage of the application wall or CPU execution time.

## Report Formatters Shipped With Nsight Systems

The following formats are available in Nsight Systems

### Column

Usage:

```
column[:nohdr][:nolimit][:nofmt][:<width>[:<width>]...]
```

Arguments

- ▶ nohdr : Do not display the header
- ▶ nolimit : Remove 100 character limit from auto-width columns Note: This can result in extremely wide columns.
- ▶ nofmt : Do not reformat numbers.
- ▶ <width>... : Define the explicit width of one or more columns. If the value "." is given, the column will auto-adjust. If a width of 0 is given, the column will not be displayed.

The column formatter presents data in vertical text columns. It is primarily designed to be a human-readable format for displaying data on a console display.

Text data will be left-justified, while numeric data will be right-justified. If the data overflows the available column width, it will be marked with a "..." character, to indicate

the data values were clipped. Clipping always occurs on the right-hand side, even for numeric data.

Numbers will be reformatted to make easier to visually scan and understand. This includes adding thousands-separators. This process requires that the string representation of the number is converted into its native representation (integer or floating point) and then converted back into a string representation to print. This conversion process attempts to preserve elements of number presentation, such as the number of decimal places, or the use of scientific notation, but the conversion is not always perfect (the number should always be the same, but the presentation may not be). To disable the reformatting process, use the argument **nofmt**.

If no explicit width is given, the columns auto-adjust their width based off the header size and the first 100 lines of data. This auto-adjustment is limited to a maximum width of 100 characters. To allow larger auto-width columns, pass the initial argument **nolimit**. If the first 100 lines do not calculate the correct column width, it is suggested that explicit column widths be provided.

## Table

Usage:

```
table[:nohdr][:nolimit][:nofmt][:<width>[:<width>]...]
```

Arguments

- ▶ **nohdr** : Do not display the header
- ▶ **nolimit** : Remove 100 character limit from auto-width columns Note: This can result in extremely wide columns.
- ▶ **nofmt** : Do not reformat numbers.
- ▶ **<width>...** : Define the explicit width of one or more columns. If the value "." is given, the column will auto-adjust. If a width of 0 is given, the column will not be displayed.

The table formatter presents data in vertical text columns inside text boxes. Other than the lines between columns, it is identical to the **column** formatter.

## CSV

Usage:

```
csv[:nohdr]
```

Arguments

- ▶ **nohdr** : Do not display the header

The csv formatter outputs data as comma-separated values. This format is commonly used for import into other data applications, such as spread-sheets and databases.

There are many different standards for CSV files. Most differences are in how escapes are handled, meaning data values that contain a comma or space.

This CSV formatter will escape commas by surrounding the whole value in double-quotes.

## TSV

Usage:

**tsv** [ :nohdr ] [ :esc ]

Arguments

- ▶ nohdr : Do not display the header
- ▶ esc : escape tab characters, rather than removing them

The tsv formatter outputs data as tab-separated values. This format is sometimes used for import into other data applications, such as spreadsheets and databases.

Most TSV import/export systems disallow the tab character in data values. The formatter will normally replace any tab characters with a single space. If the **esc** argument has been provided, any tab characters will be replaced with the literal characters `"\t"`.

## JSON

Usage:

**json**

Arguments: no arguments

The json formatter outputs data as an array of JSON objects. Each object represents one line of data, and uses the column names as field labels. All objects have the same fields. The formatter attempts to recognize numeric values, as well as JSON keywords, and converts them. Empty values are passed as an empty string (and not nil, or as a missing field).

At this time the formatter does not escape quotes, so if a data value includes double-quotation marks, it will corrupt the JSON file.

## HDoc

Usage:

**hdoc** [ :title=<title> ] [ :css=<URL> ]

Arguments:

- ▶ title : string for HTML document title
- ▶ css : URL of CSS document to include

The hdoc formatter generates a complete, verifiable (mostly), standalone HTML document. It is designed to be opened in a web browser, or included in a larger document via an `<iframe>`.

## HTable

Usage:

**htable**

Arguments: no arguments

The htable formatter outputs a raw HTML `<table>` without any of the surrounding HTML document. It is designed to be included into a larger HTML document. Although most web browsers will open and display the document, it is better to use the **hdoc** format for this type of use.

# Chapter 5.

## MIGRATING FROM NVIDIA NVPROF

### Using the Nsight Systems CLI nvprof Command

The **nvprof** command of the Nsight Systems CLI is intended to help former nvprof users transition to nsys. Many nvprof switches are not supported by nsys, often because they are now part of NVIDIA Nsight Compute.

The full nvprof documentation can be found at <https://docs.nvidia.com/cuda/profiler-users-guide>.

The nvprof transition guide for Nsight Compute can be found at <https://docs.nvidia.com/nsight-compute/NsightComputeCli/index.html#nvprof-guide>.

Any nvprof switch not listed below is not supported by the **nsys nvprof** command. No additional nsys functionality is available through this command. New features will not be added to this command in the future.

### CLI nvprof Command Switch Options

After choosing the **nvprof** command switch, the following options are available. When you are ready to move to using Nsight Systems CLI directly, see [Command Line Options](#) documentation for the nsys switch(es) given below. Note that the nsys implementation and output may vary from nvprof.

#### Usage.

```
nsys nvprof [options]
```

Switch	Parameters (Default in Bold)	nsys switch	Switch Description
--annotate-mpi	<b>off</b> , openmpi, mpich	--trace=mpi AND --mpi-impl	Automatically annotate MPI calls with NVTX markers. Specify the MPI

Switch	Parameters (Default in Bold)	nsys switch	Switch Description
			implementation installed on your machine. Only OpenMPI and MPICH implementations are supported.
--cpu-thread-tracing	on, <b>off</b>	--trace=osrt	Collect information about CPU thread API activity.
--profile-api-trace	none, runtime, driver, <b>all</b>	--trace=cuda	Turn on/off CUDA runtime and driver API tracing. For Nsight Systems there is no separate CUDA runtime and CUDA driver trace, so selecting <b>runtime</b> or <b>driver</b> is equivalent to selecting <b>all</b> .
--profile-from-start	<b>on</b> , off	if off use --capture-range=cudaProfilerApp	Enable/disable profiling from the start of the application. If disabled, the application can use {cu,cuda}Profiler{Start,Stop} to turn on/off profiling.
-t,--timeout	<nanoseconds> default= <b>0</b>	--duration=seconds	If greater than 0, stop the collection and kill the launched application after timeout seconds. nvprof started counting when the CUDA driver is initialized. nsys starts counting immediately.

Switch	Parameters (Default in Bold)	nsys switch	Switch Description
--cpu-profiling	on, <b>off</b>	--sampling=cpu	Turn on/off CPU profiling
--openacc-profiling	<b>on</b> , off	--trace=openacc to turn on	Enable/disable recording information from the OpenACC profiling interface. Note: OpenACC profiling interface depends on the presence of the OpenACC runtime. For supported runtimes, see <b>CUDA Trace</b> section of documentation
-o, --export-profile	<filename>	--output={filename} and/or --export=sqlite	Export named file to be imported or opened in the Nsight Systems GUI. %q{ENV_VAR} in string will be replaced with the set value of the environment variable. If not set this is an error. %h in the string is replaced with the system hostname. %% in the string is replaced with %. %p in the string is not supported currently. Any other character following % is illegal. The default is report1, with the number incrementing to avoid overwriting files, in users working directory.

Switch	Parameters (Default in Bold)	nsys switch	Switch Description
-f, --force-overwrite		--force-overwrite=true	Force overwriting all output files with same name.
-h, --help		--help	Print Nsight Systems CLI help
-V, --version		--version	Print Nsight Systems CLI version information

## Next Steps

NVIDIA Visual Profiler (NVVP) and NVIDIA nvprof are deprecated. New GPUs and features will not be supported by those tools. We encourage you to make the move to Nsight Systems now. For additional information, suggestions, and rationale, see the blog series in [Other Resources](#).

# Chapter 6.

## PROFILING IN A DOCKER ON LINUX DEVICES

### Collecting data within a Docker

The following information assumes the reader is knowledgeable regarding Docker containers. For further information about Docker use in general, see the [Docker documentation](#).

### Enable Docker Collection

When starting the Docker to perform a Nsight Systems collection, additional steps are required to enable the **perf\_event\_open** system call. This is required in order to utilize the Linux kernel's perf subsystem which provides sampling information to Nsight Systems.

There are three ways to enable the **perf\_event\_open** syscall. You can enable it by using the **--privileged=true** switch, adding **--cap-add=SYS\_ADMIN** switch to your docker run command file, or you can enable it by setting the seccomp security profile if your system meets the requirements.

Secure computing mode (seccomp) is a feature of the Linux kernel that can be used to restrict an application's access. This feature is available only if the kernel is enabled with seccomp support. To check for seccomp support:

```
$ grep CONFIG_SECCOMP= /boot/config-$(uname -r)
```

The official Docker documentation says:

```
"Seccomp profiles require seccomp 2.2.1 which is not available on Ubuntu 14.04, Debian Wheezy, or Debian Jessie. To use seccomp on these distributions, you must download the latest static Linux binaries (rather than packages)."
```

Download the default seccomp profile file, **default.json**, relevant to your Docker version. If **perf\_event\_open** is already listed in the file as guarded by **CAP\_SYS\_ADMIN**, then remove the **perf\_event\_open** line. Add the following lines under "syscalls" and save the resulting file as **default\_with\_perf.json**.

```
{
  "name": "perf_event_open",
  "action": "SCMP_ACT_ALLOW",
  "args": []
},
```

Then you will be able to use the following switch when starting the Docker to apply the new seccomp profile.

```
--security-opt seccomp=default_with_perf.json
```

### Launch Docker Collection

Here is an example command that has been used to launch a Docker for testing with Nsight Systems:

```
sudo nvidia-docker run --network=host --security-opt  
seccomp=default_with_perf.json --rm -ti caffe-demo2 bash
```

There is a known issue where Docker collections terminate prematurely with older versions of the driver and the CUDA Toolkit. If collection is ending unexpectedly, please update to the latest versions.

After the Docker has been started, use the Nsight Systems CLI to launch a collection within the Docker. The resulting .qdstrm file can be imported into the Nsight Systems host like any other CLI result.


# Chapter 7.

## DIRECT3D TRACE

Nsight Systems has the ability to trace both the Direct3D 11 API and the Direct3D 12 API on Windows targets.

### 7.1. D3D11 API trace

Nsight Systems can capture information about Direct3D 11 API calls made by the profiled process. This includes capturing the execution time of D3D11 API functions, performance markers, and frame durations.




#### SLI Trace

Trace SLI queries and peer-to-peer transfers of D3D11 applications. Requires SLI hardware and an active SLI profile definition in the NVIDIA console.


### 7.2. D3D12 API Trace

Direct3D 12 is a low-overhead 3D graphics and compute API for Microsoft Windows. Information about Direct3D 12 can be found at the [Direct3D 12 Programming Guide](#).

Nsight Systems can capture information about Direct3D 12 usage by the profiled process. This includes capturing the execution time of D3D12 API functions, corresponding workloads executed on the GPU, performance markers, and frame durations.



The Command List Creation row displays time periods when command lists were being created. This enables developers to improve their application's multi-threaded command list creation. Command list creation time period is measured between the call to `ID3D12GraphicsCommandList::Reset` and the call to `ID3D12GraphicsCommandList::Close`.



The GPU row shows an aggregated view of D3D12 API calls and GPU workloads. Note that not all D3D12 API calls are logged.




A Command Queue row is displayed for each D3D12 command queue created by the profiled application. The row's header displays the queue's running index and its type (Direct, Compute, Copy).

- ▶ Command Queue 0 (Compute)
- ▶ Command Queue 1 (Direct)

The DX12 API Memory Ops row displays all API memory operations and non-persistent resource mappings. Event ranges in the row are color-coded by the heap type they belong to (Default, Readback, Upload, Custom, or CPU-Visible VRAM), with usage warnings highlighted in yellow. A breakdown of the operations can be found by expanding the row to show rows for each individual heap type.

The following operations and warnings are shown:


- ▶ Calls to **ID3D12Device::CreateCommittedResource**, **ID3D12Device4::CreateCommittedResource1**, and **ID3D12Device8::CreateCommittedResource2**
  - ▶ A warning will be reported if **D3D12\_HEAP\_FLAG\_CREATE\_NOT\_ZEROED** is not set in the method's **HeapFlags** parameter
- ▶ Calls to **ID3D12Device::CreateHeap** and **ID3D12Device4::CreateHeap1**
  - ▶ A warning will be reported if **D3D12\_HEAP\_FLAG\_CREATE\_NOT\_ZEROED** is not set in the **Flags** field of the method's **pDesc** parameter
- ▶ Calls to **ID3D12Resource::ReadFromSubResource**
  - ▶ A warning will be reported if the read is to a **D3D12\_CPU\_PAGE\_PROPERTY\_WRITE\_COMBINE** CPU page or from a **D3D12\_HEAP\_TYPE\_UPLOAD** resource
- ▶ Calls to **ID3D12Resource::WriteToSubResource**
  - ▶ A warning will be reported if the write is from a **D3D12\_CPU\_PAGE\_PROPERTY\_WRITE\_BACK** CPU page or to a **D3D12\_HEAP\_TYPE\_READBACK** resource
- ▶ Calls to **ID3D12Resource::Map** and **ID3D12Resource::Unmap** will be matched into [Map, Unmap] ranges for non-persistent mappings. If a mapping range is nested, only the most external range (reference count = 1) will be shown.



The API row displays time periods where **ID3D12CommandQueue::ExecuteCommandLists** was called. The GPU Workload row displays time periods where workloads were executed by the GPU. The workload's type (Graphics, Compute, Copy, etc.) is displayed on the bar representing the workload's GPU execution.



In addition, you can see the PIX command queue CPU-side performance markers, GPU-side performance markers and the GPU Command List performance markers, each in their row.




Clicking on a GPU workload highlights the corresponding `ID3D12CommandQueue::ExecuteCommandLists`, `ID3D12GraphicsCommandList::Reset` and `ID3D12GraphicsCommandList::Close` API calls, and vice versa.



Detecting which CPU thread was blocked by a fence can be difficult in complex apps that run tens of CPU threads. The timeline view displays the 3 operations involved:

- ▶ The CPU thread pushing a signal command and fence value into the command queue. This is displayed on the DX12 Synchronization sub-row of the calling thread.
- ▶ The GPU executing that command, setting the fence value and signaling the fence. This is displayed on the GPU Queue Synchronization sub-row.
- ▶ The CPU thread calling a Win32 wait API to block-wait until the fence is signaled. This is displayed on the Thread's OS runtime libraries row.

Clicking one of these will highlight it and the corresponding other two calls.




## Chapter 8. WDDM QUEUES

The Windows Display Driver Model (WDDM) architecture uses queues to send work packets from the CPU to the GPU. Each D3D device in each process is associated with one or more contexts. Graphics, compute, and copy commands that the profiled application uses are associated with a context, batched in a command buffer, and pushed into the relevant queue associated with that context.

Nsight Systems can capture the state of these queues during the trace session.

Enabling the "Collect additional range of ETW events" option will also capture extended DxxKrnL events such as context status, allocations, sync wait, signal events, etc.



A command buffer in a WDDM queues may have one the following types:

- ▶ Render
- ▶ Deferred
- ▶ System
- ▶ MMIOFlip
- ▶ Wait
- ▶ Signal
- ▶ Device
- ▶ Software

It may also be marked as a Present buffer, indicating that the application has finished rendering and requests to display the source surface.

See the Microsoft documentation for the WDDM architecture and the `DXGKETW_QUEUE_PACKET_TYPE` enumeration.

To retain the .etl trace files captured, so that they can be viewed in other tools (e.g. GPUView), change the "Save ETW log files in project folder" option under "Profile Behavior" in Nsight Systems's global Options dialog. The .etl files will appear in the same folder as the .nsys-rep file, accessible by right-clicking the report in the Project Explorer and choosing "Show in Folder...". Data collected from each ETW provider will appear in its own .etl file, and an additional .etl file named "Report XX-Merged-\*.etl", containing the events from all captured sources, will be created as well.


# Chapter 9.

## VULKAN API TRACE

### 9.1. Vulkan Overview

Vulkan is a low-overhead, cross-platform 3D graphics and compute API, targeting a wide variety of devices from PCs to mobile phones and embedded platforms. The Vulkan API is defined by the Khronos Group. Information about Vulkan and the Khronos Group can be found at the [Khronos Vulkan Site](#).

Nsight Systems can capture information about Vulkan usage by the profiled process. This includes capturing the execution time of Vulkan API functions, corresponding GPU workloads, debug util labels, and frame durations. Vulkan profiling is supported on both Windows and x86 Linux operating systems.



The Command Buffer Creation row displays time periods when command buffers were being created. This enables developers to improve their application's multi-threaded command buffer creation. Command buffer creation time period is measured between the call to **vkBeginCommandBuffer** and the call to **vkEndCommandBuffer**.



The Swap chains row displays the available swap chains and the time periods where **vkQueuePresentKHR** was executed on each swap chain.




A Queue row is displayed for each Vulkan queue created by the profiled application. The API sub-row displays time periods where `vkQueueSubmit` was called. The GPU Workload sub-row displays time periods where workloads were executed by the GPU.



In addition, you can see [Vulkan debug util labels](#) on both the CPU and the GPU.



Clicking on a GPU workload highlights the corresponding `vkQueueSubmit` call, and vice versa.




## 9.2. Pipeline Creation Feedback

When tracing target application calls to Vulkan pipeline creation APIs, Nsight Systems leverages the Pipeline Creation Feedback extension to collect more details about the duration of individual pipeline creation stages.

See [Pipeline Creation Feedback extension](#) for details about this extension.

Vulkan pipeline creation feedback is available on NVIDIA driver release 435 or later.



## 9.3. Vulkan GPU Trace Notes

- ▶ Vulkan GPU trace is available only when tracing apps that use NVIDIA GPUs.
- ▶ The endings of Vulkan Command Buffers execution ranges on Compute and Transfer queues may appear earlier on the timeline than their actual occurrence.

# Chapter 10.


## STUTTER ANALYSIS

### Stutter Analysis Overview

Nsight Systems on Windows targets displays stutter analysis visualization aids for profiled graphics applications that use either OpenGL, D3D11, D3D12 or Vulkan, as detailed below in the following sections.

## 10.1. FPS Overview


The Frame Duration section displays frame durations on both the CPU and the GPU.



The frame duration row displays live FPS statistics for the current timeline viewport. Values shown are:

1. Number of CPU frames shown of the total number captured
2. Average, minimal, and maximal CPU frame time of the currently displayed time range
3. Average FPS value for the currently displayed frames
4. The 99th percentile value of the frame lengths (such that only 1% of the frames in the range are longer than this value).

The values will update automatically when scrolling, zooming or filtering the timeline view.



The stutter row highlights frames that are significantly longer than the other frames in their immediate vicinity.

The stutter row uses an algorithm that compares the duration of each frame to the median duration of the surrounding 19 frames. Duration difference under 4 milliseconds is never considered a stutter, to avoid cluttering the display with frames whose absolute stutter is small and not noticeable to the user.

For example, if the stutter threshold is set at 20%:

1. Median duration is 10 ms. Frame with 13 ms time will not be reported (relative difference > 20%, absolute difference < 4 ms)
2. Median duration is 60 ms. Frame with 71 ms time will not be reported (relative difference < 20%, absolute difference > 4 ms)
3. Median duration is 60 ms. Frame with 80 ms is a stutter (relative difference > 20%, absolute difference > 4 ms, both conditions met)


### OSC detection

The "19 frame window median" algorithm by itself may not work well with some cases of "oscillation" (consecutive fast and slow frames), resulting in some false positives. The median duration is not meaningful in cases of oscillation and can be misleading.


To address the issue and identify if oscillating frames, the following method is applied:

1. For every frame, calculate the median duration, 1st and 3rd quartiles of 19-frames window.
2. Calculate the delta and ratio between 1st and 3rd quartiles.
3. If the 90th percentile of 3rd – 1st quartile delta array > 4 ms AND the 90th percentile of 3rd/1st quartile array > 1.2 (120%) then mark the results with "OSC" text.

Right-clicking the Frame Duration row caption lets you choose the target frame rate (30, 60, 90 or custom frames per second).



By clicking the Customize FPS Display option, a customization dialog pops up. In the dialog, you can now define the frame duration threshold to customize the view of the potentially problematic frames. In addition, you can define the threshold for the stutter analysis frames.



Frame duration bars are color coded:

- ▶ Green, the frame duration is shorter than required by the target FPS ratio.
- ▶ Yellow, duration is slightly longer than required by the target FPS rate.
- ▶ Red, duration far exceeds that required to maintain the target FPS rate.

The CPU Frame Duration row displays the CPU frame duration measured between the ends of consecutive frame boundary calls:

- ▶ The OpenGL frame boundaries are **eglSwapBuffers/glxSwapBuffers/SwapBuffers** calls.
- ▶ The D3D11 and D3D12 frame boundaries are **IDXGISwapChainX::Present** calls.
- ▶ The Vulkan frame boundaries are **vkQueuePresentKHR** calls.

The GPU Frame Duration row displays the time measured between

- ▶ The start time of the first GPU workload execution of this frame.
- ▶ The start time of the first GPU workload execution of the next frame.

## Reflex SDK


NVIDIA Reflex SDK is a series of NVAPI calls that allow applications to integrate the Ultra Low Latency driver feature more directly into their game to further optimize synchronization between simulation and rendering stages and lower the latency between user input and final image rendering. For more details about Reflex SDK, see [Reflex SDK Site](#).

Nsight Systems will automatically capture NVAPI functions when either Direct3D 11, Direct3D 12, or Vulkan API trace are enabled.

The Reflex SDK row displays timeline ranges for the following types of latency markers:

- ▶ RenderSubmit.
- ▶ Simulation.
- ▶ Present.
- ▶ Driver.
- ▶ OS Render Queue.


► GPU Render.



## 10.2. Frame Health

The Frame Health row displays actions that took significantly a longer time during the current frame, compared to the median time of the same actions executed during the surrounding 19-frames. This is a great tool for detecting the reason for frame time stuttering. Such actions may be: shader compilation, present, memory mapping, and more. Nsight Systems measures the accumulated time of such actions in each frame. For example: calculating the accumulated time of shader compilations in each frame and comparing it to the accumulated time of shader compilations in the surrounding 19 frames.

Example of a Vulkan frame health row:





## 10.3. GPU Memory Utilization


The Memory Utilization row displays the amount of used local GPU memory and the commit limit for each GPU.



Note that this is not the same as the CUDA kernel memory allocation graph, see [CUDA GPU Memory Graph](#) for that functionality.

## 10.4. Vertical Synchronization

The VSYNC rows display when the monitor's vertical synchronizations occur.




# Chapter 11.

## OPENMP TRACE

Nsight Systems for Linux x86\_64 and Power targets is capable of capturing information about OpenMP events. This functionality is built on the OpenMP Tools Interface (OMPT), full support is available only for runtime libraries supporting tools interface defined in OpenMP 5.0 or greater.

As an example, LLVM OpenMP runtime library partially implements tools interface. If you use PGI compiler <= 20.4 to build your OpenMP applications, add -mp=libomp switch to use LLVM OpenMP runtime and enable OMPT based tracing. If you use Clang, make sure the LLVM OpenMP runtime library you link to was compiled with tools interface enabled.



Only a subset of the OMPT callbacks are processed:

```
ompt_callback_parallel_begin
ompt_callback_parallel_end
ompt_callback_sync_region
ompt_callback_task_create
ompt_callback_task_schedule
ompt_callback_implicit_task
ompt_callback_master
ompt_callback_reduction
ompt_callback_task_create
ompt_callback_cancel
ompt_callback_mutex_acquire, ompt_callback_mutex_acquired
ompt_callback_mutex_acquired, ompt_callback_mutex_released
ompt_callback_mutex_released
ompt_callback_work
ompt_callback_dispatch
ompt_callback_flush
```

**Note:**

The  
raw  
OMPT  
events  
are



used  
to  
generate  
ranges  
indicating  
the  
runtime  
of  
OpenMP  
operations  
and  
constructs.

Example screenshot:




# Chapter 12.

## OS RUNTIME LIBRARIES TRACE

On Linux, OS runtime libraries can be traced to gather information about low-level userspace APIs. This traces the system call wrappers and thread synchronization interfaces exposed by the C runtime and POSIX Threads (pthread) libraries. This does not perform a complete runtime library API trace, but instead focuses on the functions that can take a long time to execute, or could potentially cause your thread be unscheduled from the CPU while waiting for an event to complete. OS runtime trace is not available for Windows targets.

OS runtime tracing complements and enhances sampling information by:


1. Visualizing when the process is communicating with the hardware, controlling resources, performing multi-threading synchronization or interacting with the kernel scheduler.
2. Adding additional thread states by correlating how OS runtime libraries traces affect the thread scheduling:
  - ▶ **Waiting** — the thread is not scheduled on a CPU, it is inside of an OS runtime libraries trace and is believed to be waiting on the firmware to complete a request.
  - ▶ **In OS runtime library function** — the thread is scheduled on a CPU and inside of an OS runtime libraries trace. If the trace represents a system call, the process is likely running in kernel mode.
3. Collecting backtraces for long OS runtime libraries call. This provides a way to gather blocked-state backtraces, allowing you to gain more context about why the thread was blocked so long, yet avoiding unnecessary overhead for short events.



To enable OS runtime libraries tracing from Nsight Systems:

**CLI** — Use the **-t**, **--trace** option with the **osrt** parameter. See [Command Line Options](#) for more information.

**GUI** — Select the **Collect OS runtime libraries trace** checkbox.



You can also use **Skip if shorter than**. This will skip calls shorter than the given threshold. Enabling this option will improve performances as well as reduce noise on the timeline. We strongly encourage you to skip OS runtime libraries call shorter than 1 µs.

## 12.1. Locking a Resource

The functions listed below receive a special treatment. If the tool detects that the resource is already acquired by another thread and will induce a blocking call, we always trace it. Otherwise, it will never be traced.

```
pthread_mutex_lock
pthread_rwlock_rdlock
pthread_rwlock_wrlock
pthread_spin_lock
sem_wait
```

Note that even if a call is determined as potentially blocking, there is a chance that it may not actually block after a few cycles have elapsed. The call will still be traced in this scenario.

## 12.2. Limitations

- Nsight Systems only traces syscall wrappers exposed by the C runtime. It is not able to trace syscall invoked through assembly code.

- ▶ Additional thread states, as well as backtrace collection on long calls, are only enabled if sampling is turned on.
- ▶ It is not possible to configure the depth and duration threshold when collecting backtraces. Currently, only OS runtime libraries calls longer than 80  $\mu$ s will generate a backtrace with a maximum of 24 frames. This limitation will be removed in a future version of the product.
- ▶ It is required to compile your application and libraries with the **-funwind-tables** compiler flag in order for Nsight Systems to unwind the backtraces correctly.

## 12.3. OS Runtime Libraries Trace Filters

The OS runtime libraries tracing is limited to a select list of functions. It also depends on the version of the C runtime linked to the application.

## 12.4. OS Runtime Default Function List

### Libc system call wrappers

```
accept
accept4
acct
alarm
arch_prctl
bind
bpf
brk
chroot
clock_nanosleep
connect
copy_file_range
creat
creat64
dup
dup2
dup3
epoll_ctl
epoll_pwait
epoll_wait
fallocate
fallocate64
fcntl
fdatasync
flock
fork
fsync
ftruncate
futex
ioctl
ioperm
iopl
kill
killpg
listen
membarrier
mlock
mlock2
mlockall
mmap
mmap64
mount
move_pages
mprotect
mq_notify
mq_open
mq_receive
mq_send
mq_timedreceive
mq_timedsend
mremap
msgctl
msgget
msgrcv
msgsnd
msync
munmap
nanosleep
nfsservctl
open
open64
openat
openat64
pause
pipe
pipe2
pivot_root
poll
```

## POSIX Threads

```
pthread_barrier_wait  
pthread_cancel  
pthread_cond_broadcast  
pthread_cond_signal  
pthread_cond_timedwait  
pthread_cond_wait  
pthread_create  
pthread_join  
pthread_kill  
pthread_mutex_lock  
pthread_mutex_timedlock  
pthread_mutex_trylock  
pthread_rwlock_rdlock  
pthread_rwlock_timedrdlock  
pthread_rwlock_timedwrlock  
pthread_rwlock_tryrdlock  
pthread_rwlock_trywrlock  
pthread_rwlock_wrlock  
pthread_spin_lock  
pthread_spin_trylock  
pthread_timedjoin_np  
pthread_tryjoin_np  
pthread_yield  
sem_timedwait  
sem_trywait  
sem_wait
```

**I/O**

```

aio_fsync
aio_fsync64
aio_suspend
aio_suspend64
fclose
fcloseall
fflush
fflush_unlocked
fgetc
fgetc_unlocked
fgets
fgets_unlocked
fgetwc
fgetwc_unlocked
fgetws
fgetws_unlocked
flockfile
fopen
fopen64
fputc
fputc_unlocked
fputs
fputs_unlocked
fputwc
fputwc_unlocked
fputws
fputws_unlocked
fread
fread_unlocked
freopen
freopen64
ftrylockfile
fwrite
fwrite_unlocked
getc
getc_unlocked
getdelim
getline
getw
getwc
getwc_unlocked
lockf
lockf64
mkfifo
mkfifoat
posix_fallocate
posix_fallocate64
putc
putc_unlocked
putwc
putwc_unlocked

```

**Miscellaneous**

```

forkpty
popen
posix_spawn
posix_spawnnp
sigwait
sigwaitinfo
sleep
system
usleep

```

# Chapter 13.

## NVTX TRACE

The NVIDIA Tools Extension Library (NVTX) is a powerful mechanism that allows users to manually instrument their application. Nsight Systems can then collect the information and present it on the timeline.

Nsight Systems supports version 3.0 of the NVTX specification.

The following features are supported:

- Domains

```
nvtxDomainCreate(), nvtxDomainDestroy()
```

```
nvtxDomainRegisterString()
```

- Push-pop ranges (nested ranges that start and end in the same thread).

```
nvtxRangePush(), nvtxRangePushEx()
```

```
nvtxRangePop()
```

```
nvtxDomainRangePushEx()
```

```
nvtxDomainRangePop()
```

- Start-end ranges (ranges that are global to the process and are not restricted to a single thread)

```
nvtxRangeStart(), nvtxRangeStartEx()
```

```
nvtxRangeEnd()
```

```
nvtxDomainRangeStartEx()
```

```
nvtxDomainRangeEnd()
```

- Marks

```
nvtxMark(), nvtxMarkEx()
```

```
nvtxDomainMarkEx()
```

- Thread names

```
nvtxNameOsThread()
```

- Categories

```
nvtxNameCategory()
```

```
nvtxDomainNameCategory()
```

To learn more about specific features of NVTX, please refer to the NVTX header file: **nvToolsExt.h** or the [NVTX documentation](#).

To use NVTX in your application, follow these steps:

1. Add `#include "nvtx3/nvToolsExt.h"` in your source code. The nvtx3 directory is located in the Nsight Systems package in the Target-<architecture>/nvtx/include directory and is available via github at <http://github.com/NVIDIA/NVTX>.
2. Add the following compiler flag: `-ldl`
3. Add calls to the NVTX API functions. For example, try adding `nvtxRangePush("main")` in the beginning of the `main()` function, and `nvtxRangePop()` just before the return statement in the end.

For convenience in C++ code, consider adding a wrapper that implements RAII (resource acquisition is initialization) pattern, which would guarantee that every range gets closed.

4. In the project settings, select the **Collect NVTX trace** checkbox.
5. If you are on Linux on Tegra, if launching the application manually, the following environment variables should be specified:

- ▶ For ARMv7 processes:

```
NVTX_INJECTION32_PATH=/opt/nvidia/nsight_systems/libToolsInjection32.so
```


- ▶ For ARMv8 processes:


```
NVTX_INJECTION64_PATH=/opt/nvidia/nsight_systems/libToolsInjection64.so
```

In addition, by enabling the "Insert NVTX Marker hotkey" option it is possible to add NVTX markers to a running non-console applications by pressing the F11 key. These will appear in the report under the NVTX Domain named "HotKey markers".

Typically calls to NVTX functions can be left in the source code even if the application is not being built for profiling purposes, since the overhead is very low when the profiler is not attached.

NVTX is not intended to annotate very small pieces of code that are being called very frequently. A good rule of thumb to use: if code being annotated usually takes less than 1 microsecond to execute, adding an NVTX range around this code should be done carefully.






## NVTX Domains and Categories


NVTX domains enable scoping of annotations. Unless specified differently, all events and annotations are in the default domain. Additionally, categories can be used to group events.

Nsight Systems gives the user the ability to include or exclude NVTX events from a particular domain. This can be especially useful if you are profiling across multiple libraries and are only interested in nvtx events from some of them.



This functionality is also available from the CLI. See the CLI documentation for `--nvtx-domain-include` and `--nvtx-domain-exclude` for more details.

Categories that are set in by the user will be recognized and displayed in the GUI.




# Chapter 14.

## CUDA TRACE


Nsight Systems is capable of capturing information about CUDA execution in the profiled process.

The following information can be collected and presented on the timeline in the report:

- ▶ CUDA API trace — trace of CUDA Runtime and CUDA Driver calls made by the application.
  - ▶ CUDA Runtime calls typically start with **cuda** prefix (e.g. **cudaLaunch**).
  - ▶ CUDA Driver calls typically start with **cu** prefix (e.g. **cuDeviceGetCount**).
- ▶ CUDA workload trace — trace of activity happening on the GPU, which includes memory operations (e.g., Host-to-Device memory copies) and kernel executions. Within the threads that use the CUDA API, additional child rows will appear in the timeline tree.
- ▶ On Nsight Systems Workstation Edition, cuDNN and cuBLAS API tracing and OpenACC tracing.




Near the bottom of the timeline row tree, the GPU node will appear and contain a CUDA node. Within the CUDA node, each CUDA context used within the process will be shown along with its corresponding CUDA streams. Streams will contain memory operations and kernel launches on the GPU. Kernel launches are represented by blue, while memory transfers are displayed in red.




The easiest way to capture CUDA information is to launch the process from Nsight Systems, and it will setup the environment for you. To do so, simply set up a normal launch and select the **Collect CUDA trace** checkbox.

For Nsight Systems Workstation Edition this looks like:



For Nsight Systems Embedded Platforms Edition this looks like:



Additional configuration parameters are available:

- ▶ **Collect backtraces for API calls longer than X seconds** - turns on collection of CUDA API backtraces and sets the minimum time a CUDA API event must take before its backtraces are collected. Setting this value too low can cause high application overhead and seriously increase the size of your results file.
- ▶ **Flush data periodically** — specifies the period after which an attempt to flush CUDA trace data will be made. Normally, in order to collect full CUDA trace, the application needs to finalize the device used for CUDA work (call

`cudaDeviceReset()`, and then let the application gracefully exit (as opposed to crashing).

This option allows flushing CUDA trace data even before the device is finalized. However, it might introduce additional overhead to a random CUDA Driver or CUDA Runtime API call.

- ▶ **Skip some API calls** — avoids tracing insignificant CUDA Runtime API calls (namely, `cudaConfigureCall()`, `cudaSetupArgument()`, `cudaHostGetDevicePointers()`). Not tracing these functions allows Nsight Systems to significantly reduce the profiling overhead, without losing any interesting data. (See CUDA Trace Filters, below)
- ▶ **Collect GPU Memory Usage** - collects information used to generate a graph of CUDA allocated memory across time. Note that this will increase overhead. See section on **CUDA GPU Memory Allocation Graph** below.
- ▶ **Collect Unified Memory CPU page faults** - collects information on page faults that occur when CPU code tries to access a memory page that resides on the device. See section on **Unified Memory CPU Page Faults** in the **Unified Memory Transfer Trace** documentation below.
- ▶ **Collect Unified Memory GPU page faults** - collects information on page faults that occur when GPU code tries to access a memory page that resides on the CPU. See section on **Unified Memory GPU Page Faults** in the **Unified Memory Transfer Trace** documentation below.
- ▶ For Nsight Systems Workstation Edition, **Collect cuDNN trace**, **Collect cuBLAS trace**, **Collect OpenACC trace** - selects which (if any) extra libraries that depend on CUDA to trace.

OpenACC versions 2.0, 2.5, and 2.6 are supported when using PGI runtime version 15.7 or greater and not compiling statically. In order to differentiate constructs, a PGI runtime of 16.1 or later is required. Note that Nsight Systems Workstation Edition does not support the GCC implementation of OpenACC at this time.


- ▶ For Nsight Systems Embedded Platforms Edition if desired, the target application can be manually set up to collect CUDA trace. To capture information about CUDA execution, the following requirements should be satisfied:
  - ▶ The profiled process should be started with the specified environment variable, depending on the architecture of the process:
    - ▶ For ARMv7 (32-bit) processes: **CUDA\_INJECTION32\_PATH**, which should point to the injection library:  
`/opt/nvidia/nsight_systems/libToolsInjection32.so`
    - ▶ For ARMv8 (64-bit) processes: **CUDA\_INJECTION64\_PATH**, which should point to the injection library:  
`/opt/nvidia/nsight_systems/libToolsInjection64.so`
  - ▶ If the application is started by Nsight Systems, all required environment variables will be set automatically.

Please note that if your application crashes before all collected CUDA trace data has been copied out, some or all data might be lost and not present in the report.


## 14.1. CUDA GPU Memory Allocation Graph

When the **Collect GPU Memory Usage** option is selected from the **Collect CUDA trace** option set, Nsight Systems will track CUDA GPU memory allocations and deallocations and present a graph of this information in the timeline. This is not the same as the GPU memory graph generated during stutter analysis on the Windows target (see [Stutter Memory Trace](#))

Below, in the report on the left, memory is allocated and freed during the collection. In the report on the right, memory is allocated, but not freed during the collection.




Here is another example, where allocations are happening on multiple GPUs



## 14.2. Unified Memory Transfer Trace

For Nsight Systems Workstation Edition, Unified Memory (also called Managed Memory) transfer trace is enabled automatically in Nsight Systems when CUDA trace is selected. It incurs no overhead in programs that do not perform any Unified Memory transfers. Data is displayed in the Managed Memory area of the timeline:




**HtoD transfer** indicates the CUDA kernel accessed managed memory that was residing on the host, so the kernel execution paused and transferred the data to the device. Heavy traffic here will incur performance penalties in CUDA kernels, so consider using manual `cudaMemcpy` operations from pinned host memory instead.

**PtoP transfer** indicates the CUDA kernel accessed managed memory that was residing on a different device, so the kernel execution paused and transferred the data to this device. Heavy traffic here will incur performance penalties, so consider using manual `cudaMemcpyPeer` operations to transfer from other devices' memory instead. The row showing these events is for the destination device -- the source device is shown in the tooltip for each transfer event.

**DtoH transfer** indicates the CPU accessed managed memory that was residing on a CUDA device, so the CPU execution paused and transferred the data to system memory. Heavy traffic here will incur performance penalties in CPU code, so consider using manual `cudaMemcpy` operations from pinned host memory instead.

Some Unified Memory transfers are highlighted with red to indicate potential performance issues:





Transfers with the following migration causes are highlighted:

- ▶ **Coherence**  
Unified Memory migration occurred to guarantee data coherence. SMs (streaming multiprocessors) stop until the migration completes.
- ▶ **Eviction**  
Unified Memory migrated to the CPU because it was evicted to make room for another block of memory on the GPU. This happens due to memory overcommitment which is available on Linux with Compute Capability  $\geq 6$ .

## Unified Memory CPU Page Faults

The Unified Memory CPU page faults feature in Nsight Systems tracks the page faults that occur when CPU code tries to access a memory page that resides on the device.






## Unified Memory GPU Page Faults

The Unified Memory GPU page faults feature in Nsight Systems tracks the page faults that occur when GPU code tries to access a memory page that resides on the host.

**Note:**

Collecting Unified Memory GPU page faults can cause overhead of up to 70% in testing. Please use this functionality only

when needed.



## 14.3. CUDA Default Function List for CLI

### CUDA Runtime API

```
cudaBindSurfaceToArray
cudaBindTexture
cudaBindTexture2D
cudaBindTextureToArray
cudaBindTextureToMipmappedArray
cudaConfigureCall
cudaCreateSurfaceObject
cudaCreateTextureObject
cudaD3D10MapResources
cudaD3D10RegisterResource
cudaD3D10UnmapResources
cudaD3D10UnregisterResource
cudaD3D9MapResources
cudaD3D9MapVertexBuffer
cudaD3D9RegisterResource
cudaD3D9RegisterVertexBuffer
cudaD3D9UnmapResources
cudaD3D9UnmapVertexBuffer
cudaD3D9UnregisterResource
cudaD3D9UnregisterVertexBuffer
cudaDestroySurfaceObject
cudaDestroyTextureObject
cudaDeviceReset
cudaDeviceSynchronize
cudaEGLStreamConsumerAcquireFrame
cudaEGLStreamConsumerConnect
cudaEGLStreamConsumerConnectWithFlags
cudaEGLStreamConsumerDisconnect
cudaEGLStreamConsumerReleaseFrame
cudaEGLStreamConsumerReleaseFrame
cudaEGLStreamProducerConnect
cudaEGLStreamProducerDisconnect
cudaEGLStreamProducerReturnFrame
cudaEventCreate
cudaEventCreateFromEGLSync
cudaEventCreateWithFlags
cudaEventDestroy
cudaEventQuery
cudaEventRecord
cudaEventRecord_ptsz
cudaEventSynchronize
cudaFree
cudaFreeArray
cudaFreeHost
cudaFreeMipmappedArray
cudaGLMapBufferObject
cudaGLMapBufferObjectAsync
cudaGLRegisterBufferObject
cudaGLUnmapBufferObject
cudaGLUnmapBufferObjectAsync
cudaGLUnregisterBufferObject
cudaGraphicsD3D10RegisterResource
cudaGraphicsD3D11RegisterResource
cudaGraphicsD3D9RegisterResource
cudaGraphicsEGLRegisterImage
cudaGraphicsGLRegisterBuffer
cudaGraphicsGLRegisterImage
cudaGraphicsMapResources
cudaGraphicsUnmapResources
cudaGraphicsUnregisterResource
cudaGraphicsVDPAURegisterOutputSurface
cudaGraphicsVDPAURegisterVideoSurface
cudaHostAlloc
cudaHostRegister
cudaHostUnregister
cudaLaunch
cudaLaunchCooperativeKernel
cudaLaunchCooperativeKernelMultiDevice
```

**CUDA Primary API**

```

cu64Array3DCreate
cu64ArrayCreate
cu64D3D9MapVertexBuffer
cu64GLMapBufferObject
cu64GLMapBufferObjectAsync
cu64MemAlloc
cu64MemAllocPitch
cu64MemFree
cu64MemGetInfo
cu64MemHostAlloc
cu64Memcpy2D
cu64Memcpy2DAsync
cu64Memcpy2DUnaligned
cu64Memcpy3D
cu64Memcpy3DAsync
cu64MemcpyAtoD
cu64MemcpyDtoA
cu64MemcpyDtoD
cu64MemcpyDtoDAsync
cu64MemcpyDtoH
cu64MemcpyDtoHAsync
cu64MemcpyHtoD
cu64MemcpyHtoDAsync
cu64MemsetD16
cu64MemsetD16Async
cu64MemsetD2D16
cu64MemsetD2D16Async
cu64MemsetD2D32
cu64MemsetD2D32Async
cu64MemsetD2D8
cu64MemsetD2D8Async
cu64MemsetD32
cu64MemsetD32Async
cu64MemsetD8
cu64MemsetD8Async
cuArray3DCreate
cuArray3DCreate_v2
cuArrayCreate
cuArrayCreate_v2
cuArrayDestroy
cuBinaryFree
cuCompilePtx
cuCtxCreate
cuCtxCreate_v2
cuCtxDestroy
cuCtxDestroy_v2
cuCtxSynchronize
cuD3D10CtxCreate
cuD3D10CtxCreateOnDevice
cuD3D10CtxCreate_v2
cuD3D10MapResources
cuD3D10RegisterResource
cuD3D10UnmapResources
cuD3D10UnregisterResource
cuD3D11CtxCreate
cuD3D11CtxCreateOnDevice
cuD3D11CtxCreate_v2
cuD3D9CtxCreate
cuD3D9CtxCreateOnDevice
cuD3D9CtxCreate_v2
cuD3D9MapResources
cuD3D9MapVertexBuffer
cuD3D9MapVertexBuffer_v2
cuD3D9RegisterResource
cuD3D9RegisterVertexBuffer
cuD3D9UnmapResources
cuD3D9UnmapVertexBuffer
cuD3D9UnregisterResource
cuD3D9UnregisterVertexBuffer
cuEGLStreamConsumerAcquireFrame
cuEGLStreamConsumerConnect
cuEGLStreamConsumerConnectWithFlags
cuEGLStreamConsumerDisconnect
cuEGLStreamConsumerReleaseFrame

```

## 14.4. cuDNN Function List for X86 CLI

### cuDNN API functions

```

cudnnActivationBackward
cudnnActivationBackward_v3
cudnnActivationBackward_v4
cudnnActivationForward
cudnnActivationForward_v3
cudnnActivationForward_v4
cudnnAddTensor
cudnnBatchNormalizationBackward
cudnnBatchNormalizationBackwardEx
cudnnBatchNormalizationForwardInference
cudnnBatchNormalizationForwardTraining
cudnnBatchNormalizationForwardTrainingEx
cudnnCTCLoss
cudnnConvolutionBackwardBias
cudnnConvolutionBackwardData
cudnnConvolutionBackwardFilter
cudnnConvolutionBiasActivationForward
cudnnConvolutionForward
cudnnCreate
cudnnCreateAlgorithmPerformance
cudnnDestroy
cudnnDestroyAlgorithmPerformance
cudnnDestroyPersistentRNNPlan
cudnnDivisiveNormalizationBackward
cudnnDivisiveNormalizationForward
cudnnDropoutBackward
cudnnDropoutForward
cudnnDropoutGetReserveSpaceSize
cudnnDropoutGetStatesSize
cudnnFindConvolutionBackwardDataAlgorithm
cudnnFindConvolutionBackwardDataAlgorithmEx
cudnnFindConvolutionBackwardFilterAlgorithm
cudnnFindConvolutionBackwardFilterAlgorithmEx
cudnnFindConvolutionForwardAlgorithm
cudnnFindConvolutionForwardAlgorithmEx
cudnnFindRNNBackwardDataAlgorithmEx
cudnnFindRNNBackwardWeightsAlgorithmEx
cudnnFindRNNForwardInferenceAlgorithmEx
cudnnFindRNNForwardTrainingAlgorithmEx
cudnnFusedOpsExecute
cudnnIm2Col
cudnnLRNCrossChannelBackward
cudnnLRNCrossChannelForward
cudnnMakeFusedOpsPlan
cudnnMultiHeadAttnBackwardData
cudnnMultiHeadAttnBackwardWeights
cudnnMultiHeadAttnForward
cudnnOpTensor
cudnnPoolingBackward
cudnnPoolingForward
cudnnRNNBackwardData
cudnnRNNBackwardDataEx
cudnnRNNBackwardWeights
cudnnRNNBackwardWeightsEx
cudnnRNNForwardInference
cudnnRNNForwardInferenceEx
cudnnRNNForwardTraining
cudnnRNNForwardTrainingEx
cudnnReduceTensor
cudnnReorderFilterAndBias
cudnnRestoreAlgorithm
cudnnRestoreDropoutDescriptor
cudnnSaveAlgorithm
cudnnScaleTensor
cudnnSoftmaxBackward
cudnnSoftmaxForward
cudnnSpatialTfGridGeneratorBackward
cudnnSpatialTfGridGeneratorForward

```




# Chapter 15.

## OPENACC TRACE


Nsight Systems for Linux x86\_64 and Power targets is capable of capturing information about OpenACC execution in the profiled process.

OpenACC versions 2.0, 2.5, and 2.6 are supported when using PGI runtime version 15.7 or later. In order to differentiate constructs (see tooltip below), a PGI runtime of 16.0 or later is required. Note that Nsight Systems does not support the GCC implementation of OpenACC at this time.


Under the CPU rows in the timeline tree, each thread that uses OpenACC will show OpenACC trace information. You can click on a OpenACC API call to see correlation with the underlying CUDA API calls (highlighted in teal):




If the OpenACC API results in GPU work, that will also be highlighted:



Hovering over a particular OpenACC construct will bring up a tooltip with details about that construct:



To capture OpenACC information from the Nsight Systems GUI, select the **Collect OpenACC trace** checkbox under **Collect CUDA trace** configurations. Note that turning on OpenACC tracing will also turn on CUDA tracing.



Please note that if your application crashes before all collected OpenACC trace data has been copied out, some or all data might be lost and not present in the report.

# Chapter 16.

## OPENGL TRACE

OpenGL and OpenGL ES APIs can be traced to assist in the analysis of CPU and GPU interactions.


A few usage examples are:


1. Visualize how long **eglSwapBuffers** (or similar) is taking.
2. API trace can easily show correlations between thread state and graphics driver's behavior, uncovering where the CPU may be waiting on the GPU.
3. Spot bubbles of opportunity on the GPU, where more GPU workload could be created.
4. Use **KHR\_debug** extension to trace GL events on both the CPU and GPU.

OpenGL trace feature in Nsight Systems consists of two different activities which will be shown in the CPU rows for those threads

- ▶ **CPU trace:** interception of API calls that an application does to APIs (such as OpenGL, OpenGL ES, EGL, GLX, WGL, etc.).
- ▶ **GPU trace (or workload trace):** trace of GPU workload (activity) triggered by use of OpenGL or OpenGL ES. Since draw calls are executed back-to-back, the GPU workload trace ranges include many OpenGL draw calls and operations in order to optimize performance overhead, rather than tracing each individual operation.

To collect GPU trace, the **glQueryCounter()** function is used to measure how much time batches of GPU workload take to complete.





Ranges defined by the **KHR\_debug** calls are represented similarly to OpenGL API and OpenGL GPU workload trace. GPU ranges in this case represent *incremental draw cost*. They cannot fully account for GPUs that can execute multiple draw calls in parallel. In this case, Nsight Systems will not show overlapping GPU ranges.

## 16.1. OpenGL Trace Using Command Line

For general information on using the target CLI, see [CLI Profiling on Linux](#). For the CLI, the functions that are traced are set to the following list:

```
glWaitSync
glReadPixels
glReadnPixelsKHR
glReadnPixelsEXT
glReadnPixelsARB
glReadnPixels
glFlush
glFinishFenceNV
glFinish
glClientWaitSync
glClearTexSubImage
glClearTexImage
glClearStencil
glClearNamedFramebufferuiv
glClearNamedFramebufferiv
glClearNamedFramebufferfv
glClearNamedFramebufferfi
glClearNamedBufferSubDataEXT
glClearNamedBufferSubData
glClearNamedBufferDataEXT
glClearNamedBufferData
glClearIndex
glClearDepthx
glClearDepthf
glClearDepthdNV
glClearDepth
glClearColorx
glClearColorIuiEXT
glClearColorIiEXT
glClearColor
glClearBufferuiv
glClearBufferSubData
glClearBufferiv
glClearBufferfv
glClearBufferfi
glClearBufferData
glClearAccum
glClear
glDispatchComputeIndirect
glDispatchComputeGroupSizeARB
glDispatchCompute
glComputeStreamNV
glNamedFramebufferDrawBuffers
glNamedFramebufferDrawBuffer
glMultiDrawElementsIndirectEXT
glMultiDrawElementsIndirectCountARB
glMultiDrawElementsIndirectBindlessNV
glMultiDrawElementsIndirectBindlessCountNV
glMultiDrawElementsIndirectAMD
glMultiDrawElementsIndirect
glMultiDrawElementsEXT
glMultiDrawElementsBaseVertex
glMultiDrawElements
glMultiDrawArraysIndirectEXT
glMultiDrawArraysIndirectCountARB
glMultiDrawArraysIndirectBindlessNV
glMultiDrawArraysIndirectBindlessCountNV
glMultiDrawArraysIndirectAMD
glMultiDrawArraysIndirect
glMultiDrawArraysEXT
glMultiDrawArrays
glListDrawCommandsStatesClientNV
glFramebufferDrawBuffersEXT
glFramebufferDrawBufferEXT
glDrawTransformFeedbackStreamInstanced
glDrawTransformFeedbackStream
glDrawTransformFeedbackNV
```




# Chapter 17.

## CUSTOM ETW TRACE


Use the custom ETW trace feature to enable and collect any manifest-based ETW log. The collected events are displayed on the timeline on dedicated rows for each event type.

Custom ETW is available on Windows target machines.



The 'Add provider' dialog box is used to configure a new ETW provider. It contains the following fields and controls:


- Name:** Microsoft-Windows-Dwm-Core
- Guid:** 9E9BBA3C-2E38-40CB-99F4-9E8281425164
- Optional:**
- Buffer Size (KB):**
- Min Buffers:**
- Max Buffers:**
- Keyword:** 0x80010000007F003F
- Level:** TRACE\_LEVEL\_INFORMATION (dropdown menu)
- Flags:** Select flags (button)
- Buttons:** OK, Cancel



The 'Custom ETW Trace' window displays a table of ETW providers included in the trace. The table has the following columns: Name, GUID, Flags, Buffer Size (KB), Min Buffers, Max Buffers, and a TRAC column. The table contains one row for the provider 'Microsoft-Windows-Dwm-Core'.

Name	GUID	Flags	Buffer Size (KB)	Min Buffers	Max Buffers	TRAC
Microsoft-Windows-Dwm-Core	9E9BBA3C-2E38-...	0x0	0	0	0	TRAC

Buttons: Edit, Add, Remove



To retain the .etl trace files captured, so that they can be viewed in other tools (e.g. GPUView), change the "Save ETW log files in project folder" option under "Profile Behavior" in Nsight Systems's global Options dialog. The .etl files will appear in the same folder as the .nsys-rep file, accessible by right-clicking the report in the Project Explorer and choosing "Show in Folder...". Data collected from each ETW provider will appear in its own .etl file, and an additional .etl file named "Report XX-Merged-\*.etl", containing the events from all captured sources, will be created as well.

# Chapter 18.

## GPU METRIC SAMPLING

### Overview

GPU performance metrics sampling is intended to identify performance limiters in applications using GPU for computations and graphics. It uses periodic sampling to gather performance metrics and detailed timing statistics associated with different GPU hardware units taking advantage of specialized hardware to capture this data in a single pass with minimal overhead.

**Note:** GPU metrics sampling will give you precise device level information, but it does not know which process or context is involved. GPU context switch trace provides less precise information, but will give you process and context information.



These metrics provide an overview of GPU efficiency over time within compute, graphics, and input/output (IO) activities such as:

- ▶ **IO throughputs:** PCIe, NVLink, and GPU memory bandwidth
- ▶ **SM utilization:** SMs activity, tensor core activity, instructions issued, warp occupancy, and unassigned warp slots

It is designed to help users answer the common questions:

- ▶ Is my GPU idle?
- ▶ Is my GPU full? Enough kernel grids size and streams? Are my SMs and warp slots full?
- ▶ Am I using TensorCores?
- ▶ Is my instruction rate high?
- ▶ Am I possibly blocked on IO, or number of warps, etc

Nsight Systems GPU metric sampling is only available for Linux targets on x86-64 and aarch64 and for Windows targets. It requires NVIDIA Turing architecture or newer.

Minimum required driver versions:

- ▶ NVIDIA Turing architecture TU10x, TU11x - r440
- ▶ NVIDIA Ampere architecture GA100 - r450
- ▶ NVIDIA Ampere architecture GA100 MIG - r470 TRD1
- ▶ NVIDIA Ampere architecture GA10x - r455

**Note:** Elevated permissions are required. On Linux use sudo to elevate privileges. On Windows the user must run from an admin command prompt or accept the UAC escalation dialog. See [Permissions Issues and Performance Counters](#) for more information.

## Launching GPU Metric Sampling from the CLI

GPU performance metrics sampling is controlled with 3 CLI switches:

- ▶ `--gpu-metrics-device=[all,none,<index>]` selects GPUs to sample (default is none)
- ▶ `--gpu-metrics-set=[<index> or <alias>]` selects metric set to use (default is the 1st suitable from the list)
- ▶ `--gpu-metrics-frequency=[10,200000]` selects sampling frequency in Hz (default is 10000)

To profile with default options and sample GPU metrics on GPU #0:

```
# Must have elevated permissions (see http://nv/ERR_NVGPUCTRPERM) or be root
(Linux) or administrator (Windows)
$ nsys profile --gpu-metrics-device=0 ./my-app
```

To list the available GPUs, use:

```
$ nsys profile --gpu-metrics-device=help
Possible --gpu-metrics-device values are:
  0: Quadro GV100 [0000:17:00.0]
  1: GeForce RTX 2070 SUPER [0000:65:00.0]
  all: Select all supported GPUs
  none: Disable GPU metrics [Default]
```

By default the first **metric set** which supports the selected GPU is used. But you can manually select another metric set from the list. To see available metric sets use:

```
$ nsys profile --gpu-metrics-set=help
Possible --gpu-metrics-set values are:
[0] [tu10x]      General Metrics for NVIDIA TU10x (any frequency)
[1] [tu11x]      General Metrics for NVIDIA TU11x (any frequency)
[2] [ga100]      General Metrics for NVIDIA GA100 (any frequency)
[3] [ga10x]      General Metrics for NVIDIA GA10x (any frequency)
[4] [tu10x-gfxt] Graphics Throughput Metrics for NVIDIA TU10x (frequency
>= 10kHz)
[5] [ga10x-gfxt] Graphics Throughput Metrics for NVIDIA GA10x (frequency
>= 10kHz)
[6] [ga10x-gfxact] Graphics Async Compute Triage Metrics for NVIDIA GA10x
(frequency >= 10kHz)
```


By default metrics **sampling frequency** is set to 10 kHz. But you can manually set it from 10 Hz to 200 kHz using

```
--gpu-metrics-frequency=<value>
```

## Launching GPU Metric Sampling from the GUI


For commands to launch GPU metric sampling from the CLI with examples, see the [CLI documentation](#).

When launching analysis in Nsight Systems, select **Collect GPU Metrics**.



Select the **GPUs** dropdown to pick which GPUs you wish to sample.

Select the **Metric set** dropdown to choose which available metric set you would like to sample.



Note that metric sets for GPUs that are not being sampled will be greyed out.

## Sampling frequency

Sampling frequency can be selected from the range of 10 Hz - 200 kHz. The default value is 10 kHz.

The maximum sampling frequency without buffer overflow events depends on GPU (SM count), GPU load intensity, and overall system load. The bigger the chip and the higher the load, the lower the maximum sampling frequency without buffer overflow errors. If you need higher frequency, you can increase it until you get "Buffer overflow" message in the Diagnostics Summary report page. If you observe buffer overflow ranges on timeline, lower the sampling frequency.

Each metric set has a recommended sampling frequency range in its description. These ranges are approximate. If you observe **Inconsistent Data** ranges on timeline, please try closer to the recommended frequency.

## Available Metrics

### ► GPC Clock Frequency - `gpc__cycles_elapsed.avg.per_second`

The average GPC clock frequency in hertz. In public documentation the GPC clock may be called the "Application" clock, "Graphic" clock, "Base" clock, or "Boost" clock.

**Note:** The collection mechanism for GPC can result in a small fluctuation between samples.

### ► SYS Clock Frequency - `sys__cycles_elapsed.avg.per_second`

The average SYS clock frequency in hertz. The GPU front end (command processor), copy engines, and the performance monitor run at the SYS clock. On Turing and NVIDIA GA100 GPUs the GPU metrics sampling frequency is based upon a period of SYS clocks (not time) so samples per second will vary with SYS clock. On NVIDIA GA10x GPUs the GPU metrics sampling rate is based upon a fixed frequency clock. The maximum sampling rate scales linearly with the SYS clock.

### ► GR Active - `gr__cycles_active.sum.pct_of_peak_sustained_elapsed`

The percentage of cycles the graphics/compute engine is active. The graphics/compute engine is active if there is any work in the graphics pipe or if the compute pipe is processing work.

GA100 MIG - MIG is not yet supported. This counter will report the activity of the primary GR engine.

### ► Sync Compute In Flight -

`gr__dispatch_cycles_active_queue_sync.avg.pct_of_peak_sustained_elapsed`

The percentage of cycles with synchronous compute in flight.

CUDA: CUDA will only report synchronous queue in the case of MPS configured with 64 sub-context. Synchronous refers to work submitted in VEID=0.

Graphics: This will be true if any compute work submitted from the direct queue is in flight.

### ► Async Compute in Flight -

`gr__dispatch_cycles_active_queue_async.avg.pct_of_peak_sustained_elapsed`

The percentage of cycles with asynchronous compute in flight.

CUDA: CUDA will only report all compute work as asynchronous. The one exception is if MPS is configured and all 64 sub-context are in use. 1 sub-context (VEID=0) will report as synchronous.

Graphics: This will be true if any compute work submitted from a compute queue is in flight.

► **Draw Started - `fe__draw_count.avg.pct_of_peak_sustained_elapsed`**

The ratio of draw calls issued to the graphics pipe to the maximum sustained rate of the graphics pipe.

**Note:** The percentage will always be very low as the front end can issue draw calls significantly faster than the pipe can execute the draw call. The rendering of this row will be changed to help indicate when draw calls are being issued.

► **Dispatch Started -**

**`gr__dispatch_count.avg.pct_of_peak_sustained_elapsed`**

The ratio of compute grid launches (dispatches) to the compute pipe to the maximum sustained rate of the compute pipe.

**Note:** The percentage will always be very low as the front end can issue grid launches significantly faster than the pipe can execute the draw call. The rendering of this row will be changed to help indicate when grid launches are being issued.

► **Vertex/Tess/Geometry Warps in Flight -**

**`tpc__warps_active_shader_vtg_realtime.avg.pct_of_peak_sustained_elapsed`**

The ratio of active vertex, geometry, tessellation, and meshlet shader warps resident on the SMs to the maximum number of warps per SM as a percentage.

► **Pixel Warps in Flight -**

**`tpc__warps_active_shader_ps_realtime.avg.pct_of_peak_sustained_elapsed`**

The ratio of active pixel/fragment shader warps resident on the SMs to the maximum number of warps per SM as a percentage.

► **Compute Warps in Flight -**

**`tpc__warps_active_shader_cs_realtime.avg.pct_of_peak_sustained_elapsed`**

The ratio of active compute shader warps resident on the SMs to the maximum number of warps per SM as a percentage.

► **Active SM Unused Warp Slots -**

**`tpc__warps_inactive_sm_active_realtime.avg.pct_of_peak_sustained_elapsed`**

The ratio of inactive warp slots on the SMs to the maximum number of warps per SM as a percentage. This is an indication of how many more warps may fit on the SMs if occupancy is not limited by a resource such as max warps of a shader type, shared memory, registers per thread, or thread blocks per SM.

► **Idle SM Unused Warp Slots -**

**`tpc__warps_inactive_sm_idle_realtime.avg.pct_of_peak_sustained_elapsed`**

The ratio of inactive warp slots due to idle SMs to the the maximum number of warps per SM as a percentage.

This is an indicator that the current workload on the SM is not sufficient to put work on all SMs. This can be due to:

- ▶ CPU starving the GPU
- ▶ current work is too small to saturate the GPU
- ▶ current work is trailing off but blocking next work
- ▶ **SM Active - `sm__cycles_active.avg.pct_of_peak_sustained_elapsed`**  
 The ratio of cycles SMs had at least 1 warp in flight (allocated on SM) to the number of cycles as a percentage. A value of 0 indicates all SMs were idle (no warps in flight). A value of 50% can indicate some gradient between all SMs active 50% of the sample period or 50% of SMs active 100% of the sample period.
- ▶ **SM Issue - `sm__inst_executed_realtime.avg.pct_of_peak_sustained_elapsed`**  
 The ratio of cycles that SM sub-partitions (warp schedulers) issued an instruction to the number of cycles in the sample period as a percentage.
- ▶ **Tensor Active - `sm__pipe_tensor_cycles_active_realtime.avg.pct_of_peak_sustained_elapsed`**  
 The ratio of cycles the SM tensor pipes were active issuing tensor instructions to the number of cycles in the sample period as a percentage.  
  
 TU102/4/6: This metric is not available on TU10x for periodic sampling. Please see Tensor Active/FP16 Active.
- ▶ **Tensor Active / FP16 Active - `sm__pipe_shared_cycles_active_realtime.avg.pct_of_peak_sustained_elapsed`**  
 TU102/4/6 only  
  
 The ratio of cycles the SM tensor pipes or FP16x2 pipes were active issuing tensor instructions to the number of cycles in the sample period as a percentage.
- ▶ **VRAM Bandwidth - `dram__throughput.avg.pct_of_peak_sustained_elapsed`**  
 The ratio of cycles the GPU device memory controllers were actively performing read or write operations to the number of cycles in the sample period as a percentage.
- ▶ **NVLINK bytes received - `nvlrx__bytes.avg.pct_of_peak_sustained_elapsed`**  
 The ratio of bytes received on the NVLINK interface to the maximum number of bytes receivable in the sample period as a percentage. This value includes protocol overhead.
- ▶ **NVLINK bytes transmitted - `nvltx__bytes.avg.pct_of_peak_sustained_elapsed`**  
 The ratio of bytes transmitted on the NVLINK interface to the maximum number of bytes transmittable in the sample period as a percentage. This value includes protocol overhead.
- ▶ **PCIe Read Throughput - `pcie__read_bytes.avg.pct_of_peak_sustained_elapsed`**  
 The ratio of bytes received on the PCIe interface to the maximum number of bytes receivable in the sample period as a percentage. The theoretical value is calculated

based upon the PCIe generation and number of lanes. This value includes protocol overhead.

► **PCIe Write Throughput -**

**pcie\_\_write\_bytes.avg.pct\_of\_peak\_sustained\_elapsed**

The ratio of bytes received on the PCIe interface to the maximum number of bytes receivable in the sample period as a percentage. The theoretical value is calculated based upon the PCIe generation and number of lanes. This value includes protocol overhead.

## Exporting and Querying Data

It is possible to access the metric values for automated processing using the Nsight Systems CLI export capabilities.

An example that extracts values of "SM Active":

```
$ nsys export -t sqlite report.nsys-rep
$ sqlite3 report.sqlite "SELECT rawTimestamp, CAST(JSON_EXTRACT(data, '$.
\"SM Active\"') as INTEGER) as value FROM GENERIC_EVENTS WHERE value != 0 LIMIT
10"

309277039|80
309301295|99
309325583|99
309349776|99
309373872|60
309397872|19
309421840|100
309446000|100
309470096|100
309494161|99
```

An overview of the contents of the data stored in each event (JSON):

```
$ sqlite3 report.sqlite "SELECT data FROM GENERIC_EVENTS LIMIT 1"
{
  "Unallocated Warps in Active SM": "0",
  "Compute Warps In Flight": "52",
  "Pixel Warps In Flight": "0",
  "Vertex\Tess\Geometry Warps In Flight": "0",
  "Total SM Occupancy": "52",
  "GR Active (GE\CE)": "100",
  "Sync Compute In Flight": "0",
  "Async Compute In Flight": "98",
  "NVLINK bytes received": "0",
  "NVLINK bytes transmitted": "0",
  "PCIe Rx Throughput": "0",
  "PCIe Tx Throughput": "1",
  "DRAM Read Throughput": "0",
  "DRAM Write Throughput": "0",
  "Tensor Active \ FP16 Active": "0",
  "SM Issue": "10",
  "SM Active": "52"
}
```

Values are integer percentages (0..100)

## Limitations

- ▶ If metrics sets with NVLink are used but the links are not active, they may appear as fully utilized.
- ▶ Only one tool that subscribes to these counters can be used at a time, therefore, Nsight Systems GPU metric sampling cannot be used at the same time as the following tools:

- ▶ Nsight Graphics
- ▶ Nsight Compute
- ▶ DCGM (Data Center GPU Manager)

Use the following command:

- ▶ `dcgmi profile --pause`
- ▶ `dcgmi profile --resume`


Or API:

- ▶ `dcgmProfPause`
- ▶ `dcgmProfResume`
- ▶ Non-NVIDIA products which use:
  - ▶ CUPTI sampling used directly in the application. CUPTI trace is okay (although it will block Nsight Systems CUDA trace)
  - ▶ DCGM library
- ▶ Nsight Systems limits the amount of memory that can be used to store GPU metrics sampling data. Analysis with higher sampling rates or on GPUs with more SMs has a risk of filling these buffers. This will lead to gaps with long samples on timeline. If you select that area on the timeline you will see that the counters will pause and remain at a steady state for a while. Future releases will reduce the frequency of this happening and better present these periods.


# Chapter 19.

## NVIDIA VIDEO CODEC SDK TRACE

Nsight Systems for x86 Linux and Windows targets can trace calls from the NV Video Codec SDK. This software trace can be launched from the GUI or using the **--trace nvvideo** from the CLI



On the timeline, calls on the CPU to the NV Encoder API and NV Decoder API will be shown.



## 19.1. NV Encoder API Functions Traced by Default

```

NvEncodeAPICreateInstance
nvEncOpenEncodeSession
nvEncGetEncodeGUIDCount
nvEncGetEncodeGUIDs
nvEncGetEncodeProfileGUIDCount
nvEncGetEncodeProfileGUIDs
nvEncGetInputFormatCount
nvEncGetInputFormats
nvEncGetEncodeCaps
nvEncGetEncodePresetCount
nvEncGetEncodePresetGUIDs
nvEncGetEncodePresetConfig
nvEncGetEncodePresetConfigEx
nvEncInitializeEncoder
nvEncCreateInputBuffer
nvEncDestroyInputBuffer
nvEncCreateBitstreamBuffer
nvEncDestroyBitstreamBuffer
nvEncEncodePicture
nvEncLockBitstream
nvEncUnlockBitstream
nvEncLockInputBuffer
nvEncUnlockInputBuffer
nvEncGetEncodeStats
nvEncGetSequenceParams
nvEncRegisterAsyncEvent
nvEncUnregisterAsyncEvent
nvEncMapInputResource
nvEncUnmapInputResource
nvEncDestroyEncoder
nvEncInvalidateRefFrames
nvEncOpenEncodeSessionEx
nvEncRegisterResource
nvEncUnregisterResource
nvEncReconfigureEncoder
nvEncCreateMVBuffer
nvEncDestroyMVBuffer
nvEncRunMotionEstimationOnly
nvEncGetLastErrorString
nvEncSetIOCUDAStreams
nvEncGetSequenceParamEx

```

## 19.2. NV Decoder API Functions Traced by Default

```
cuvidCreateVideoSource  
cuvidCreateVideoSourceW  
cuvidDestroyVideoSource  
cuvidSetVideoSourceState  
cudaVideoState  
cuvidGetSourceVideoFormat  
cuvidGetSourceAudioFormat  
cuvidCreateVideoParser  
cuvidParseVideoData  
cuvidDestroyVideoParser  
cuvidCreateDecoder  
cuvidDestroyDecoder  
cuvidDecodePicture  
cuvidGetDecodeStatus  
cuvidReconfigureDecoder  
cuvidMapVideoFrame  
cuvidUnmapVideoFrame  
cuvidMapVideoFrame64  
cuvidUnmapVideoFrame64  
cuvidCtxLockCreate  
cuvidCtxLockDestroy  
cuvidCtxLock  
cuvidCtxUnlock
```

## 19.3. NV JPEG API Functions Traced by Default

```
nvjpegBufferDeviceCreate
nvjpegBufferDeviceDestroy
nvjpegBufferDeviceRetrieve
nvjpegBufferPinnedCreate
nvjpegBufferPinnedDestroy
nvjpegBufferPinnedRetrieve
nvjpegCreate
nvjpegCreateEx
nvjpegCreateSimple
nvjpegDecode
nvjpegDecodeBatched
nvjpegDecodeBatchedEx
nvjpegDecodeBatchedInitialize
nvjpegDecodeBatchedPreAllocate
nvjpegDecodeBatchedSupported
nvjpegDecodeBatchedSupportedEx
nvjpegDecodeJpeg
nvjpegDecodeJpegDevice
nvjpegDecodeJpegHost
nvjpegDecodeJpegTransferToDevice
nvjpegDecodeParamsCreate
nvjpegDecodeParamsDestroy
nvjpegDecodeParamsSetAllowCMYK
nvjpegDecodeParamsSetOutputFormat
nvjpegDecodeParamsSetROI
nvjpegDecodeParamsSetScaleFactor
nvjpegDecoderCreate
nvjpegDecoderDestroy
nvjpegDecoderJpegSupported
nvjpegDecoderStateCreate
nvjpegDestroy
nvjpegEncodeGetBufferSize
nvjpegEncodeImage
nvjpegEncodeRetrieveBitstream
nvjpegEncodeRetrieveBitstreamDevice
nvjpegEncoderParamsCopyHuffmanTables
nvjpegEncoderParamsCopyMetadata
nvjpegEncoderParamsCopyQuantizationTables
nvjpegEncoderParamsCreate
nvjpegEncoderParamsDestroy
nvjpegEncoderParamsSetEncoding
nvjpegEncoderParamsSetOptimizedHuffman
nvjpegEncoderParamsSetQuality
nvjpegEncoderParamsSetSamplingFactors
nvjpegEncoderStateCreate
nvjpegEncoderStateDestroy
nvjpegEncodeYUV, (nvjpegHandle_t handle
nvjpegGetCudartProperty
nvjpegGetDeviceMemoryPadding
nvjpegGetImageInfo
nvjpegGetPinnedMemoryPadding
nvjpegGetProperty
nvjpegJpegStateCreate
nvjpegJpegStateDestroy
nvjpegJpegStreamCreate
nvjpegJpegStreamDestroy
nvjpegJpegStreamGetChromaSubsampling
nvjpegJpegStreamGetComponentDimensions
nvjpegJpegStreamGetComponentNum
nvjpegJpegStreamGetFrameDimensions
nvjpegJpegStreamGetJpegEncoding
nvjpegJpegStreamParse
nvjpegJpegStreamParseHeader
nvjpegSetDeviceMemoryPadding
nvjpegSetPinnedMemoryPadding
nvjpegStateAttachDeviceBuffer
nvjpegStateAttachPinnedBuffer
```

# Chapter 20.

## NETWORK COMMUNICATION PROFILING

Nsight Systems can be used to profile several popular network communication protocols. To enable this, please select the **Communication profiling options** dropdown.

▶	<input checked="" type="checkbox"/> Sample target process
▶	<input checked="" type="checkbox"/> Collect CPU context switch trace
▶	<input checked="" type="checkbox"/> Collect OS runtime libraries trace
▶	<input checked="" type="checkbox"/> Collect CUDA trace
▶	<input type="checkbox"/> Collect OpenMP trace
▶	<input type="checkbox"/> Collect GPU context switch trace
▶	<input type="checkbox"/> Collect GPU metrics
▶	<input type="checkbox"/> Collect NVTX trace
▶	<input type="checkbox"/> Collect OpenGL trace
▶	<input type="checkbox"/> Collect Vulkan trace
▶	Communication profiling options (MPI, SHMEM, UCX)

Then select the libraries you would like to trace:

Communication profiling options (MPI, SHMEM, UCX)

Trace API calls into communication libraries.

☐ MPI

Select the MPI implementation used by the target application to trace a default set of MPI calls. If no MPI implementation is selected, NVIDIA Nsight Systems tries to automatically detect it based on the dynamic linker's search path. If this fails, Open MPI is used. If the application uses another MPI implementation, see the documentation for additional setup required to trace MPI. Note that NVTX tracing will also be enabled on selecting MPI tracing.

☒ Open MPI

☐ MPICH and its derivatives

☐ OpenSHMEM

OpenSHMEM is a library interface specification for parallel programming in the Partitioned Global Address Space (PGAS). NVIDIA Nsight Systems supports collecting and visualizing a default set of OpenSHMEM API calls. Note that selecting OpenSHMEM also enables NVTX tracing.

☐ UCX

UCX is an open-source communication framework which acts as a common library and API for several higher level communication libraries, e.g. for Open MPI, MPICH and NCCL. Note that selecting UCX also enables NVTX tracing.

☐ Skip stage tracking of UCP non-blocking communication

## 20.1. MPI API Trace

For Linux x86\_64 and Power targets, Nsight Systems is capable of capturing information about the MPI APIs executed in the profiled process. It has built-in API trace support only for the OpenMPI and MPICH implementations of MPI and only for a default list of synchronous APIs.

☒ Collect MPI trace


Select the MPI implementation used by the target application to trace a default set of synchronous MPI calls. If the application uses a different MPI implementation, see the documentation for additional setup required to trace MPI. Note that NVTX tracing will also be enabled on selecting MPI tracing.

☒ OpenMPI

☐ MPICH and its derivatives

☒ Collect NVTX trace

If you require more control over the list of traced APIs or if you are using a different MPI implementation, see [github nvtx pmpi wrappers](#). You can use this documentation to generate a shared object to wrap a list of synchronous MPI APIs with NVTX using the MPI profiling interface (PMPI). If you set your LD\_PRELOAD environment variable to the path of that object, Nsight Systems will capture and report the MPI API trace information when NVTX tracing is enabled.



## MPI Communication Parameters

Nsight Systems can now get additional information about MPI communication parameters. For this initial release, the parameters are only visible in the mouseover tooltips or in the eventlog. This means that the data is only available via the GUI. Future versions of the tool will export this information into the SQLite data files for postrun analysis.

In order to fully interpret MPI communications, data for all ranks associated with a communication operation must be loaded into Nsight Systems.

Here is an example of MPI\_COMM\_WORLD data. This does not require any additional team data, since local rank is the same as global rank.

(Screenshot shows communication parameters for an MPI\_Bcast call on rank 3)

**Events View**

Name:

Name
MPI_Init
MPI_Recv
<b>MPI_Bcast</b>
MPI_Bcast
MPI_Recv
MPI_Finalize

**Description:**

**MPI\_Bcast**  
 Begins: 0,164935s  
 Ends: 0,165045s (+109,210 µs)  
 Thread: 1342434  
 Bytes sent: 0  
 Bytes received: 4  
 Root: 0  
 MPI\_COMM\_WORLD

When only part of an MPI communication is loaded into Nsight Systems the following information is available.

- ▶ Right-hand screenshot shows a reused communicator handle (last number increased).
- ▶ Encoding: MPI\_COMM[\*team size]\*global-group-root-rank\*.group-ID\*

**Events View**

Name:

#	Name	Start	Description:
3	MPI_Bcast	0,06235	MPI_Send Begins: 0,062627s Ends: 0,062628s (+1,771 µs) Thread: 978418 Tag: 42 Bytes sent: 4 Destination: 1 MPI_COMM[2]1.0
4	<b>MPI_Send</b>	0,06262	
5	MPI_Bcast	0,06262	
6	MPI_Send	0,06272	
7	MPI_Bcast	0,06272	
8	MPI_Finalize	0,06272	

**Events View**

Name:

#	Name	Start	Description:
3	MPI_Bcast	0,06235	MPI_Send Begins: 0,0627267s Ends: 0,062728s (+1,314 µs) Thread: 978418 Tag: 42 Bytes sent: 4 Destination: 1 MPI_COMM[2]1.1
4	MPI_Send	0,06262	
5	MPI_Bcast	0,06262	
6	<b>MPI_Send</b>	0,06272	
7	MPI_Bcast	0,06272	
8	MPI_Finalize	0,06272	

When all reports are loaded into Nsight Systems:

- ▶ World rank is shown in addition to group-local rank "(world rank X)"
- ▶ Encoding: MPI\_COMM[\*team size\*]{rank0, rank1, ...}
- ▶ At most 8 ranks are shown (the numbers represent world ranks, the position in the list is the group-local rank)

**Events View**

Name:

Name	Description:
MPI_Init	MPI_Recv Begins: 0,16549s Ends: 0,165492s (+1,837 µs) Thread: 1047429 Tag: 42 Bytes received: 4 Source: 0 (world rank 2) MPI_COMM[2]{2, 3}
MPI_Recv	
MPI_Bcast	
MPI_Bcast	
<b>MPI_Recv</b>	
MPI_Send	

**Events View**

Name:

#	Name	Description:
1	MPI_Init	MPI_Send Begins: 0,165609s Ends: 0,165612s (+2,577 µs) Thread: 1047429 Tag: 48 Bytes sent: 4 Destination: 7 (world rank 2) MPI_COMM[10]{9, 8, 7, 6, 5, 4, 3, 2, ...}
2	MPI_Recv	
3	MPI_Bcast	
4	MPI_Bcast	
5	MPI_Recv	
6	<b>MPI_Send</b>	

NVTX tracing is automatically enabled when MPI trace is turned on.

## 20.2. OpenSHMEM Library Trace

If OpenSHMEM library trace is selected Nsight Systems will trace the subset of OpenSHMEM API functions that are most likely be involved in performance bottlenecks. To keep overhead low Nsight Systems does not trace all functions.

### OpenSHMEM 1.5 Functions Not Traced

```
shmem_my_pe
shmem_n_pes
shmem_global_exit
shmem_pe_accessible
shmem_addr_accessible
shmem_ctx_{create,destroy,get_team}
shmem_global_exit
shmem_info_get_{version,name}
shmem_{my_pe,n_pes,pe_accessible,ptr}
shmem_query_thread
shmem_team_{create_ctx,destroy}
shmem_team_get_config
shmem_team_{my_pe,n_pes,translate_pe}
shmem_team_split_{2d,strided}
shmem_test*
```

## 20.3. UCX Library Trace

If UCX library trace is selected Nsight Systems will trace the subset of functions of the UCX protocol layer UCP that are most likely be involved in performance bottlenecks. To keep overhead low Nsight Systems does not trace all functions.

**UCX functions traced:**

```

ucp_am_send_nb[x]
ucp_am_recv_data_nbx
ucp_am_data_release
ucp_atomic_{add{32,64},cswap{32,64},fadd{32,64},swap{32,64}}
ucp_atomic_{post,fetch_nb,op_nbx}
ucp_cleanup
ucp_config_{modify,read,release}
ucp_disconnect_nb
ucp_dt_{create,generic,destroy}
ucp_ep_{create,destroy,modify_nb,close_nbx}
ucp_ep_flush[{_nb,_nbx}]
ucp_listener_{create,destroy,query,reject}
ucp_mem_{advise,map,unmap,query}
ucp_{put,get}[_nbi]
ucp_{put,get}_nb[x]
ucp_request_{alloc,cancel,check_status,is_completed}
ucp_rkey_{buffer_release,destroy,pack,ptr}
ucp_stream_data_release
ucp_stream_recv_{data_nb,request_test}
ucp_stream_{send,recv}_nb[x]
ucp_stream_worker_poll
ucp_tag_msg_recv_nb[x]
ucp_tag_probe_nb
ucp_tag_{send,recv}_nbr
ucp_tag_{send,recv}_nb[x]
ucp_tag_recv_request_test
ucp_tag_send_sync_nb[x]
ucp_worker_{create,destroy,get_address,get_efd,arm,fence,wait,signal,wait_mem}
ucp_worker_flush[{_nb,_nbx}]
ucp_worker_set_am_{handler,recv_handler}

```

**UCX Functions Not Traced:**

```

ucp_config_print
ucp_conn_request_query
ucp_context_{query,print_info}
ucp_get_version[_string]
ucp_ep_{close_nb,print_info,rkey_unpack}
ucp_mem_print_info
ucp_request_{test,free,release}
ucp_worker_{progress,query,release_address,print_info}

```

Additional API functions from other UCX layers may be added in a future version of the product.

## 20.4. NVIDIA NVSHMEM and NCCL Trace

The NVIDIA network communication libraries NVSHMEM and NCCL have been instrumented using NVTX annotations. To enable tracing these libraries in Nsight Systems, turn on NVTX tracing in the GUI or CLI. To enable the NVTX instrumentation of the NVSHMEM library, make sure that the environment variable **NVSHMEM\_NVTX** is set properly, e.g. **NVSHMEM\_NVTX=common**.

## 20.5. NIC Metric Sampling


This feature is experimental.

### Overview

NVIDIA ConnectX smart network interface cards (smart NICs) offer advanced hardware offloads and accelerations for network operations. Viewing smart NICs metrics, on Nsight Systems timeline, enables developers to better understand their application's network usage. Developers can use this information to optimize the application's performance.

### Examples

- ▶ The **Bytes sent/msec** and the **Bytes received/msec** metrics enables identifying idle and busy NIC times.
  - ▶ Developers may shift network operations from busy to idle times to reduce network congestion and latency.
  - ▶ Developers can use idle NIC times to send additional data without reducing application performance.
- ▶ CNPs (congestion notification packets) received/sent metrics may explain network latencies. A developer seeing the time periods when the network was congested may rewrite his algorithm to avoid the observed congestions.
- ▶ Comparing the ratio between bytes sent and packets sent can give developers a hint about the average packet size their application is using. The larger the packet size, the higher the practical bandwidth.



### Available Metrics

- ▶ **Bytes sent** - Number of bytes sent through all NIC ports.
- ▶ **Packets sent** - Number of packets sent through all NIC ports.
- ▶ **Bytes received** - Number of bytes received by all NIC ports.
- ▶ **Packets received** - Number of packets received by all NIC ports.
- ▶ **CNPs sent** - Number of congestion notification packets sent by the NIC.
- ▶ **CNPs received** - Number of congestion notification packets received and handled by the NIC.

### Collecting NIC Metrics Using the Command Line

To collect NIC performance metric, using Nsight Systems CLI, add the `--nic-metrics` command line switch:

```
nsys profile --nic-metrics my_app
```

### System Requirements

NIC metrics collection is supported on:

- ▶ NVIDIA ConnectX 3 boards or newer
- ▶ Linux x86\_64 machines, having minimum Linux kernel 4.12 and minimum MLNX\_OFED 4.1.

### Limitations

- ▶ Nsight Systems 2021.5.1 only supports Infiniband metrics.
- ▶ Launch the following command, which will install all the required libraries in system directories:

# Chapter 21.

## READING YOUR REPORT IN GUI

### 21.1. Generating a New Report

Users can generate a new report by stopping a profiling session. If a profiling session has been canceled, a report will not be generated, and all collected data will be discarded.

A new **.nsys-rep** file will be created and put into the same directory as the project file (**.qdpproj**).

### 21.2. Opening an Existing Report

An existing **.nsys-rep** file can be opened using **File > Open....**

### 21.3. Sharing a Report File

Report files (**.nsys-rep**) are self-contained and can be shared with other users of Nsight Systems. The only requirement is that the same or newer version of Nsight Systems is always used to open report files.


Project files (**.qdpproj**) are currently not shareable, since they contain full paths to the report files.

To quickly navigate to the directory containing the report file, right click on it in the Project Explorer, and choose **Show in folder...** in the context menu.

### 21.4. Report Tab

While generating a new report or loading an existing one, a new tab will be created. The most important parts of the report tab are:

- ▶ **View selector** — Allows switching between *Analysis Summary*, *Timeline View*, *Diagnostics Summary*, and *Symbol Resolution Logs* views.



- ▶ **Timeline** — This is where all charts are displayed.
- ▶ **Function table** — Located below the timeline, it displays statistical information about functions in the target application in multiple ways.

Additionally, the following controls are available:

- ▶ **Zoom slider** — Allows you to vertically zoom the charts on the timeline.

## 21.5. Analysis Summary View

This view shows a summary of the profiling session. In particular, it is useful to review the project configuration used to generate this report. Information from this view can be selected and copied using the mouse cursor.

## 21.6. Timeline View

The timeline view consists of two main controls: the timeline at the top, and a bottom pane that contains the events view and the function table. In some cases, when sampling of a process has not been enabled, the function table might be empty and hidden.

The bottom view selector sets the view that is displayed in the bottom pane.



### 21.6.1. Timeline

Timeline is a versatile control that contains a tree-like **hierarchy** on the left, and corresponding *charts* on the right.

Contents of the hierarchy depend on the project settings used to collect the report. For example, if a certain feature has not been enabled, corresponding rows will not be shown on the timeline.

To generate a timeline screenshot without opening the full GUI, use the command


```
nsys-ui.exe --screenshot filename.nsys-rep
```

To display trace events in the Events View right-click a timeline row and select the “Show in Events View” command. The events of the selected row and all of its sub-rows will be displayed in the Events View.

If a timeline row has been selected for display in the Events View then double-clicking a timeline item on that row will automatically scroll the content of the Events View to make the corresponding Events View item visible and select it.

## Row Height

Several of the rows in the timeline use height as a way to model the percent utilization of resources. This gives the user insight into what is going on even when the timeline is zoomed all the way out.



In this picture you see that for kernel occupation there is a colored bar of variable height.

Nsight Systems calculates the average occupancy for the period of time represented by particular pixel width of screen. It then uses that average to set the top of the colored section. So, for instance, if 25% of that timeslice the kernel is active, the bar goes 25% of the distance to the top of the row.

In order to make the difference clear, if the percentage of the row height is non-zero, but would be represented by less than one vertical pixel, Nsight Systems displays it as one pixel high. The gray height represents the maximum usage in that time range.

This row height coding is used in the CPU utilization, thread and process occupancy, kernel occupancy, and memory transfer activity rows.

## 21.6.2. Events View

The Events View provides a tabular display of the trace events. The view contents can be searched and sorted.

Double-clicking an item in the Events View automatically focuses the Timeline View on the corresponding timeline item.

API calls, GPU executions, and debug markers that occurred within the boundaries of a debug marker are displayed nested to that debug marker. Multiple levels of nesting are supported.

Events view recognizes these types of debug markers:

- ▶ NVTX
- ▶ Vulkan VK\_EXT\_debug\_marker markers, VK\_EXT\_debug\_utils labels
- ▶ PIX events and markers
- ▶ OpenGL KHR\_debug markers

#	Name	Duration	TID	GPU	Context	Start	
39	ID3D12GraphicsCommandList::Reset	13.300 µs	2092	-	-	0.0016661s	
40	Scene Render	352.100 µs	2092	-	-	0.0017093s	
41	RenderLightShadows	1.900 µs	2092	-	-	0.0017207s	
43	Z PrePass	80.300 µs	2092	-	-	0.0017286s	
49	Generate SSAO	121.700 µs	2092	-	-	0.0018155s	
57	Render Shadow Map	39.100 µs	2092	-	-	0.0019445s	
59	Raytrace	68.600 µs	2092	-	-	0.0019903s	
64	Marker End	-	2092	-	-	0.0020614s	
65	ID3D12GraphicsCommandList::Close	12.400 µs	2092	-	-	0.0020753s	
66	ID3D12CommandQueue::ExecuteCommandLists	69.800 µs	2092	-	-	0.0020892s	
67	ntdll.dll!0x7ff9a47ff3b4	-	2092	-	-	0.0021694s	
68	ID3D12GraphicsCommandList::Reset	10.300 µs	2092	-	-	0.0021988s	
69	Post Effects	61.300 µs	2092	-	-	0.0022258s	
75	ID3D12GraphicsCommandList::Close	7.100 µs	2092	-	-	0.0022964s	
76	ID3D12CommandQueue::ExecuteCommandLists	33.300 µs	2092	-	-	0.0023048s	
77	ntdll.dll!0x7ff9a47ff3b4	-	2092	-	-	0.0023465s	

Call to: ID3D12CommandQueue::ExecuteCommandLists

■ DX12 API calls

Begins: 0.0020892s

Ends: 0.002159s (+69.800 µs)

Correlation IDs: {30507, 30507}

You can copy and paste from the events view by highlighting rows, using **Shift** or **Ctrl** to enable multi-select. Right clicking on the selection will give you a copy option.


Events View					Name	
#	Name	Start	Duration	TID		
4	fopen	0.347611s	5.921 µs	178685		
5	fclose	0.347628s	1.724 µs	178685		
6	open64	0.347636s	11.501 µs	178685		
7	fcntl	0.347649s	1.002 µs	178685		
8	ioctl	0.347652s	3.176 µs	178685		
9	open	0.347656s	8.686 µs	178685		
10	read	0.347666s	3.647 µs	178685		
11	ioctl	0.347675s	1.122 µs	178685		
12	ioctl	0.347678s	27.541 µs	178685		
13	ioctl	0.347707s	6.141 µs	178685		
14	ioctl	0.347713s	16.040 µs	178685		

Highlight Selected on Timeline

Show Current on Timeline

Copy Selected

Pasting into text gives you a tab separated view:




\*Untitled - Notepad

Name	Start	Duration	TID
fcntl	0.347649s	1.002 μs	178685
open	0.347656s	8.686 μs	178685
read	0.347666s	3.647 μs	178685
ioctl	0.347675s	1.122 μs	178685
ioctl	0.347678s	27.541 μs	178685


Ln 6, Col 33    100%    Windows (CRLF)    UTF-8

Pasting into spreadsheet properly copies into rows and columns:



	A	B	C	D
1	Name	Start	Duration	TID
2	fcntl	0.347649s	1.002 μs	178685
3	open	0.347656s	8.686 μs	178685
4	read	0.347666s	3.647 μs	178685
5	ioctl	0.347675s	1.122 μs	178685
6	ioctl	0.347678s	27.541 μs	178685
7				

### 21.6.3. Function Table Modes



The function table can work in three modes:


- ▶ **Top-Down View** — In this mode, expanding top-level functions provides information about the *callee* functions. One of the top-level functions is typically the main function of your application, or another entry point defined by the runtime libraries.
- ▶ **Bottom-Up View** — This is a reverse of the Top-Down view. On the top level, there are functions directly hit by the sampling profiler. To explore all possible call chains leading to these functions, you need to expand the subtrees of the top-level functions.
- ▶ **Flat View** — This view enumerates all functions ever observed by the profiler, even if they have never been directly hit, but just appeared somewhere on the call stack. This view typically provides a high-level overview of which parts of the code are CPU-intensive.

Each of the views helps understand particular performance issues of the application being profiled. For example:

- ▶ When trying to find specific bottleneck functions that can be optimized, the Bottom-Up view should be used. Typically, the top few functions should be examined. Expand them to understand in which contexts they are being used.
- ▶ To navigate the call tree of the application and while generally searching for algorithms and parts of the code that consume unexpectedly large amount of CPU time, the Top-Down view should be used.
- ▶ To quickly assess which parts of the application, or high level parts of an algorithm, consume significant amount of CPU time, use the Flat view.

The Top-Down and Bottom-Up views have *Self* and *Total* columns, while the Flat view has a *Flat* column. It is important to understand the meaning of each of the columns:


- ▶ Top-Down view
  - ▶ **Self** column denotes the relative amount of time spent executing instructions of this particular function.
  - ▶ **Total** column shows how much time has been spent executing this function, including all other functions called from this one. Total values of sibling rows sum up to the Total value of the parent row, or 100% for the top-level rows.
- ▶ Bottom-Up view
  - ▶ **Self** column for *top-level rows*, as in the Top-Down view, shows how much time has been spent directly in this function. Self times of all top-level rows add up to 100%.
  - ▶ **Self** column for *children rows* breaks down the value of the parent row based on the various call chains leading to that function. Self times of sibling rows add up to the value of the parent row.
- ▶ Flat view
  - ▶ **Flat** column shows how much time this function has been anywhere on the call stack. Values in this column do not add up or have other significant relationships.






Contents of the symbols table is tightly related to the timeline. Users can apply and modify filters on the timeline, and they will affect which information is displayed in the symbols table:

- ▶ **Per-thread filtering** — Each thread that has sampling information associated with it has a checkbox next to it on the timeline. Only threads with selected checkboxes are represented in the symbols table.
- ▶ **Time filtering** — A time filter can be setup on the timeline by pressing the left mouse button, dragging over a region of interest on the timeline, and then choosing **Filter by selection** in the dropdown menu. In this case, only sampling information collected during the selected time range will be used to build the symbols table.



for time-based filtering), the numbers in the symbols table might not be representative or accurate in some cases.

## 21.6.4. Filter Dialog



- ▶ **Collapse unresolved lines** is useful if some of the binary code does not have symbols. In this case, subtrees that consist of only unresolved symbols get collapsed in the Top-Down view, since they provide very little useful information.
- ▶ **Hide functions with CPU usage below X%** is useful for large applications, where the sampling profiler hits lots of function just a few times. To filter out the "long tail," which is typically not important for CPU performance bottleneck analysis, this checkbox should be selected.

## 21.7. Diagnostics Summary View

This view shows important messages. Some of them were generated during the profiling session, while some were added while processing and analyzing data in the report. Messages can be one of the following types:

- ▶ Informational messages

- ▶ Warnings
- ▶ Errors

To draw attention to important diagnostics messages, a summary line is displayed on the timeline view in the top right corner:



Information from this view can be selected and copied using the mouse cursor.

## 21.8. Symbol Resolution Logs View

This view shows all messages related to the process of resolving symbols. It might be useful to debug issues when some of the symbol names in the symbols table of the timeline view are unresolved.


## Chapter 22.

# ADDING REPORT TO THE TIMELINE

Starting with 2021.3, Nsight Systems can load multiple report files into a single timeline. This is a BETA feature and will be improved in the future releases. Please let us know about your experience on the forums or through **Help > Send Feedback...** in the main menu.

To load multiple report files into a single timeline, first start by opening a report as usual — using **File > Open...** from the main menu, or double clicking on a report in the Project Explorer window. Then additional report files can be loaded into the same timeline using one of the methods:

- ▶ **File > Add Report (beta)...** in the main menu, and select another report file that you want to open
- ▶ Right click on the report in the project explorer window, and click **Add Report (beta)**



### 22.1. Time Synchronization

When multiple reports are loaded into a single timeline, timestamps between them need to be adjusted, such that events that happened at the same time appear to be aligned.

Nsight Systems can automatically adjust timestamps based on **UTC time** recorded around the collection start time. This method is used by default when other more precise methods are not available. This time can be seen as **UTC time at t=0** in the *Analysis Summary* page of the report file. Refer to your OS documentation to learn how to sync the software clock using the Network Time Protocol (NTP). NTP-based time synchronization is not very precise, with the typical errors on the scale of one to tens of milliseconds.

Reports collected on the same physical machine can use synchronization based on **Timestamp Counter (TSC) values**. These are platform-specific counters, typically accessed in user space applications using the RDTSC instruction on x86\_64 architecture, or by reading the CNTVCT register on Arm64. Their values converted to nanoseconds can be seen as **TSC value at t=0** in the *Analysis Summary* page of the report file. Reports synchronized using TSC values can be aligned with nanoseconds-level precision.

TSC-based time synchronization is activated automatically, when Nsight Systems detects that the same TSC value corresponds to very close UTC times. UTC time difference must be below 1 second in this case. This method is expected to only work for reports collected on the same physical machine.

To find out which synchronization method was used, navigate to the *Analysis Summary* tab of an added report and check the **Report alignment source** property of a target. Note, that the first report won't have this parameter.

## Target

Target name	9a1630ecdd6a
Local time at t=0	2021-07-02T12:01:57.310Z
UTC time at t=0	2021-07-02T12:01:57.310Z
TSC value at t=0	1041856117291223
Report alignment source	TSC

## Target

Target name	9e2247e584e1
Local time at t=0	2021-07-02T12:01:57.311Z
UTC time at t=0	2021-07-02T12:01:57.311Z
TSC value at t=0	1041856118165144
Report alignment source	UTC

When loading multiple reports into a single timeline, it is always advisable to first check that time synchronization looks correct, by zooming into synchronization or communication events that are expected to be aligned.

## 22.2. Timeline Hierarchy

When reports are added to the same timeline Nsight Systems will automatically line them up by timestamps as described above. If you want Nsight Systems to also recognize matching process or hardware information, you will need to set environment variables **NSYS\_SYSTEM\_ID** and **NSYS\_HW\_ID** as shown below at the time of report collection (such as when using "nsys profile ..." command).

When loading a pair of given report files into the same timeline, they will be merged in one of the following configurations:

- ▶ Different hardware (default) — is used when reports are coming from different physical machines, and no hardware resources are shared in these reports. This mode is used by default, and can be additionally signalled by specifying different **NSYS\_HW\_ID** values.
- ▶ Different systems, same hardware — is used when reports are collected on different virtual machines (VMs) or containers on the same physical machine. To activate this mode, specify the same value of **NSYS\_HW\_ID** when collecting the reports.
- ▶ Same system — is used when reports are collected within the same operating system (or container) environment. In this mode a process identifier (PID) 100 will refer to the same process in both reports. To activate this mode, specify the same value of **NSYS\_SYSTEM\_ID** when collecting the reports.

The following diagrams demonstrate typical cases:




Fig 1. Different hardware (default mode)




Fig 2. Same hardware, different systems (VMs)




Fig 3. Same hardware, different systems (host and container)




Fig 4. Same system

## 22.3. Example: MPI

A typical scenario is when a computing job is run using one of the MPI implementations. Each instance of the app can be profiled separately, resulting in multiple report files. For example:

```
# Run MPI job without the profiler:
mpirun <MPI-options> ./myApp
# Run MPI job and profile each instance of the application:
mpirun <MPI-options> nsys profile -o report-%p <nsys-options> ./myApp
```

When each MPI rank runs on a different node, the command above works fine, since the default pairing mode (different hardware) will be used.

When all MPI ranks run the localhost only, use this command (value "A" was chosen arbitrarily, it can be any non-empty string):

```
NSYS_SYSTEM_ID=A mpirun <MPI-options> nsys profile -o report-%p
<nsys-options> ./myApp
```

For convenience, the MPI rank can be encoded into the report filename. Specifics depend on the MPI implementation. For Open MPI, use the following command to create report files based on the global rank value:

```
mpirun <MPI-options> nsys profile -o 'report-  
%q{OMPI_COMM_WORLD_RANK}' <nsys-options> ./myApp
```

For MPICH, use the following command:

```
mpirun <MPI-options> nsys profile -o 'report-%q{PMI_RANK}' <nsys-  
options> ./myApp
```

## 22.4. Limitations

- ▶ Only report files collected with Nsight Systems version 2021.3 and newer are fully supported.
- ▶ Sequential reports collected in a single CLI profiling session cannot be loaded into a single timeline yet.

# Chapter 23.

## USING NSIGHT SYSTEMS EXPERT SYSTEM

The Nsight Systems expert system is a feature aimed at automatic detection of performance optimization opportunities in an application's profile. It uses a set of predefined rules to determine if the application has known bad patterns.

### Using Expert System from the CLI

usage:

```
nsys [global-options] analyze [options]  
[nsys-rep-or-sqlite-file]
```

If a .nsys-rep file is given as the input file and there is no .sqlite file with the same name in the same directory, it will be generated.

**Note:** The Expert System view in the GUI will give you the equivalent command line.

### Using Expert System from the GUI

The Expert System View can be found in the same drop-down as the Events View. If there is no .sqlite file with the same name as the .nsys-rep file in the same directory, it will be generated.

The Expert System View has the following components:

1. Drop-down to select the rule to be run
2. Rule description and advice summary
3. CLI command that will give the same result
4. Table containing results of running the rule
5. Settings button that allows users to specify the rule's arguments

Expert System View

5 Settings

1 AsyncMemcpy with Pageable Memory

The following APIs use PAGEABLE memory which causes asynchronous CUDA memcpy operations to block and be executed synchronously. This leads to low GPU utilization.  
Suggestion: If applicable, use PINNED memory instead.

2

3 CLI command:  
nsys analyze -r async-memcpy-pageable /home/joan/proj/gdres/simpleMultiGPU\_multiRule.sqlite

Duration	Start	Src Kind	Dst Kind	Bytes	PID	Device ID	Context ID	Stream ID	API Name
3.841 ms	6.60844s	Device	Pageable	16.00 MiB	48558	1	2	35	cudaMemcpyAsync_v3020
3.303 ms	9.06323s	Device	Pageable	16.00 MiB	48558	2	3	50	cudaMemcpyAsync_v3020
3.292 ms	11.5212s	Device	Pageable	16.00 MiB	48558	3	4	65	cudaMemcpyAsync_v3020
3.259 ms	4.15083s	Device	Pageable	16.00 MiB	48558	0	1	20	cudaMemcpyAsync_v3020
2.417 ms	16.4269s	Device	Pageable	16.00 MiB	48558	5	6	95	cudaMemcpyAsync_v3020
2.403 ms	13.9794s	Device	Pageable	16.00 MiB	48558	4	5	80	cudaMemcpyAsync_v3020
2.390 ms	21.3225s	Device	Pageable	16.00 MiB	48558	7	8	125	cudaMemcpyAsync_v3020
2.200 ms	18.8738s	Device	Pageable	16.00 MiB	48558	6	7	110	cudaMemcpyAsync_v3020
1.883 ms	6.60654s	Pageable	Device	16.00 MiB	48558	1	2	35	cudaMemcpyAsync_v3020
1.823 ms	9.0614s	Pageable	Device	16.00 MiB	48558	2	3	50	cudaMemcpyAsync_v3020
1.822 ms	13.9776s	Pageable	Device	16.00 MiB	48558	4	5	80	cudaMemcpyAsync_v3020
1.804 ms	11.5194s	Pageable	Device	16.00 MiB	48558	3	4	65	cudaMemcpyAsync_v3020
1.796 ms	4.14902s	Pageable	Device	16.00 MiB	48558	0	1	20	cudaMemcpyAsync_v3020
1.776 ms	16.4251s	Pageable	Device	16.00 MiB	48558	5	6	95	cudaMemcpyAsync_v3020
1.768 ms	21.3207s	Pageable	Device	16.00 MiB	48558	7	8	125	cudaMemcpyAsync_v3020
1.737 ms	18.872s	Pageable	Device	16.00 MiB	48558	6	7	110	cudaMemcpyAsync_v3020

4

A context menu is available to correlate the table entry with the timeline. The options are the same as the Events View:

- Highlight selected on timeline (double-click)
- Show current on timeline (ctrl+double-click)

The highlighting is not supported for rules that do not return an event but rather an arbitrary time range (e.g. GPU utilization rules).

The CLI and GUI share the same rule scripts and messages. There might be some formatting differences between the output table in GUI and CLI.

## Expert System Rules

Rules are scripts that run on the SQLite DB output from Nsight Systems to find common improvable usage patterns.

Each rule has an advice summary with explanation of the problem found and suggestions to address it. Only the top 50 results are displayed by default.

There are currently six rules in the expert system. They are described below. Additional rules will be made available in a future version of Nsight Systems.

## CUDA Synchronous Operation Rules

### Asynchronous memcpy with pageable memory

This rule identifies asynchronous memory transfers that end up becoming synchronous if the memory is pageable. This rule is not applicable for Nsight Systems Embedded Platforms Edition

Suggestion: If applicable, use pinned memory instead



### Synchronous Memcpy

This rule identifies synchronous memory transfers that block the host.

Suggestion: Use cudaMemcpy\*Async APIs instead.

### Synchronous Memset

This rule identifies synchronous memset operations that block the host.

Suggestion: Use cudaMemset\*Async APIs instead.

### Synchronization APIs

This rule identifies synchronization APIs that block the host until all issued CUDA calls are complete.

Suggestions: Avoid excessive use of synchronization. Use asynchronous CUDA event calls, such as cudaStreamWaitEvent and cudaEventSynchronize, to prevent host synchronization.

## GPU Low Utilization Rules

Nsight Systems determines GPU utilization based on API trace data in the collection. Current rules consider CUDA, Vulkan, DX12, and OpenGL API use of the GPU.

### GPU Starvation

This rule identifies time ranges where a GPU is idle for longer than 500ms. The threshold is adjustable.

Suggestions: Use CPU sampling data, OS Runtime blocked state backtraces, and/or OS Runtime APIs related to thread synchronization to understand if a sluggish or blocked CPU is causing the gaps. Add NVTX annotations to CPU code to understand the reason behind the gaps.

Notes:

- ▶ For each process, each GPU is examined, and gaps are found within the time range that starts with the beginning of the first GPU operation on that device and ends with the end of the last GPU operation on that device.
- ▶ GPU gaps that cannot be addressed by the user are excluded. This includes:
  - ▶ Profiling overhead in the middle of a GPU gap.
  - ▶ The initial gap in the report that is seen before the first GPU operation.
  - ▶ The final gap that is seen after the last GPU operation.

### GPU Low Utilization

This rule identifies time regions with low utilization.

Suggestions: Use CPU sampling data, OS Runtime blocked state backtraces, and/or OS Runtime APIs related to thread synchronization to understand if a sluggish or blocked CPU is causing the gaps. Add NVTX annotations to CPU code to understand the reason behind the gaps.

Notes:

- ▶ For each process, each GPU is examined, and gaps are found within the time range that starts with the beginning of the first GPU operation on that device and ends with the end of the last GPU operation on that device. This time range is then divided into equal chunks, and the GPU utilization is calculated for each chunk. The utilization includes all GPU operations as well as profiling overheads that the user cannot address.
- ▶ The utilization refers to the "time" utilization and not the "resource" utilization. This rule attempts to find time gaps when the GPU is or isn't being used, but does not take into account how many GPU resources are being used. Therefore, a single running memcpy is considered the same amount of "utilization" as a huge kernel that takes over all the cores. If multiple operations run concurrently in the same chunk, their utilization will be added up and may exceed 100%.
- ▶ Chunks with an in-use percentage less than the threshold value are displayed. If consecutive chunks have a low in-use percentage, the individual chunks are coalesced into a single display record, keeping the weighted average of percentages. This is why returned chunks may have different durations.

# Chapter 24.

## IMPORT NVTXT

**ImportNvtx** is an utility which allows conversion of a **NVTXT** file to a Nsight Systems report file (\*.nsys-rep) or to merge it with an existing report file.

**Note:** NvtxImport supports custom **TimeBase** values. Only these values are supported:

- ▶ **Manual** — timestamps are set using absolute values.
- ▶ **Relative** — timestamps are set using relative values with regards to report file which is being merged with nvtx file.
- ▶ **ClockMonotonicRaw** — timestamps values in nvtx file are considered to be gathered on the same target as the report file which is to be merged with nvtx using `clock_gettime(CLOCK_MONOTONIC_RAW, ...)` call.
- ▶ **CNTVCT** — timestamps values in nvtx file are considered to be gathered on the same target as the report file which is to be merged with nvtx using CNTVCT values.

You can get usage info via help message:

Print help message:

```
-h [ --help ]
```

Show information about report file:

```
--cmd info -i [--input] arg
```

Create report file from existing nvtx file:

```
--cmd create -n [--nvtx] arg -o [--output] arg [-m [--mode] mode_name mode_args] [--target <Hw:Vm>] [--update_report_time]
```

Merge nvtx file to existing report file:

```
--cmd merge -i [--input] arg -n [--nvtx] arg -o [--output] arg [-m [--mode] mode_name mode_args] [--target <Hw:Vm>] [--update_report_time]
```

Modes description:

- ▶ **lerp** - Insert with linear interpolation  

```
--mode lerp --ns_a arg --ns_b arg [--nvtx_a arg --nvtx_b arg]
```
- ▶ **lin** - insert with linear equation  

```
--mode lin --ns_a arg --freq arg [--nvtx_a arg]
```

Modes' parameters:

- ▶ **ns\_a** - a nanoseconds value
- ▶ **ns\_b** - a nanoseconds value (greater than **ns\_a**)
- ▶ **nvtxt\_a** - an nvtxt file's time unit value corresponding to **ns\_a** nanoseconds
- ▶ **nvtxt\_b** - an nvtxt file's time unit value corresponding to **ns\_b** nanoseconds
- ▶ **freq** - the nvtxt file's timer frequency
- ▶ **--target <Hw:Vm>** - specify target id, e.g. **--target 0:1**
- ▶ **--update\_report\_time** - prolong report's profiling session time while merging if needed. Without this option all events outside the profiling session time window will be skipped during merging.

## Commands

### Info

To find out report's start and end time use **info** command.

Usage:

```
ImportNvtxt --cmd info -i [--input] arg
```

Example:

```
ImportNvtxt info Report.nsys-rep
Analysis start (ns) 83501026500000
Analysis end (ns) 83506375000000
```

### Create

You can create a report file using existing NVTXT with **create** command.

Usage:

```
ImportNvtxt --cmd create -n [--nvtxt] arg -o [--output] arg [-m [--mode]
mode_name mode_args]
```

Available modes are:

- ▶ **lerp** — insert with linear interpolation.
- ▶ **lin** — insert with linear equation.

Usage for **lerp** mode is:

```
--mode lerp --ns_a arg --ns_b arg [--nvtxt_a arg --nvtxt_b arg]
```

with:

- ▶ **ns\_a** — a nanoseconds value.
- ▶ **ns\_b** — a nanoseconds value (greater than **ns\_a**).
- ▶ **nvtxt\_a** — an nvtxt file's time unit value corresponding to **ns\_a** nanoseconds.
- ▶ **nvtxt\_b** — an nvtxt file's time unit value corresponding to **ns\_b** nanoseconds.

If **nvtxt\_a** and **nvtxt\_b** are not specified, they are respectively set to nvtxt file's minimum and maximum time value.

Usage for **lin** mode is:

```
--mode lin --ns_a arg --freq arg [--nvtxt_a arg]
```

with:

- ▶ **ns\_a** — a nanoseconds value.
- ▶ **freq** — the nvtxt file's timer frequency.
- ▶ **nvtxt\_a** — an nvtxt file's time unit value corresponding to **ns\_a** nanoseconds.

If **nvtxt\_a** is not specified, it is set to nvtxt file's minimum time value.

### Examples:

```
ImportNvtxt --cmd create -n Sample.nvtxt -o Report.nsys-rep
```

The output will be a new generated report file which can be opened and viewed by Nsight Systems.

### Merge

To merge NVTXT file with an existing report file use **merge** command.

Usage:

```
ImportNvtxt --cmd merge -i [--input] arg -n [--nvtxt] arg -o [--output] arg [-m  
[--mode] mode_name mode_args]
```

Available modes are:

- ▶ **lerp** — insert with linear interpolation.
- ▶ **lin** — insert with linear equation.

Usage for **lerp** mode is:

```
--mode lerp --ns_a arg --ns_b arg [--nvtxt_a arg --nvtxt_b arg]
```

with:

- ▶ **ns\_a** — a nanoseconds value.
- ▶ **ns\_b** — a nanoseconds value (greater than **ns\_a**).
- ▶ **nvtxt\_a** — an nvtxt file's time unit value corresponding to **ns\_a** nanoseconds.
- ▶ **nvtxt\_b** — an nvtxt file's time unit value corresponding to **ns\_b** nanoseconds.

If **nvtxt\_a** and **nvtxt\_b** are not specified, they are respectively set to nvtxt file's minimum and maximum time value.

Usage for **lin** mode is:

```
--mode lin --ns_a arg --freq arg [--nvtxt_a arg]
```

with:

- ▶ **ns\_a** — a nanoseconds value.
- ▶ **freq** — the nvtxt file's timer frequency.
- ▶ **nvtxt\_a** — an nvtxt file's time unit value corresponding to **ns\_a** nanoseconds.

If **nvtxt\_a** is not specified, it is set to nvtxt file's minimum time value.

Time values in **<filename.nvtxt>** are assumed to be nanoseconds if no mode specified.

### Example


```
ImportNvtxt --cmd merge -i Report.nsys-rep -n Sample.nvtxt -o NewReport.nsys-rep
```

# Chapter 25.

## VISUAL STUDIO INTEGRATION

NVIDIA Nsight Integration is a Visual Studio extension that allows you to access the power of Nsight Systems from within Visual Studio.

When Nsight Systems is installed along with NVIDIA Nsight Integration, Nsight Systems activities will appear under the NVIDIA Nsight menu in the Visual Studio menu bar. These activities launch Nsight Systems with the current project settings and executable.



Selecting the "Trace" command will launch Nsight Systems, create a new Nsight Systems project and apply settings from the current Visual Studio project:

- ▶ Target application path
- ▶ Command line parameters
- ▶ Working folder

If the "Trace" command has already been used with this Visual Studio project then Nsight Systems will load the respective Nsight Systems project and any previously captured trace sessions will be available for review using the Nsight Systems project explorer tree.

For more information about using Nsight Systems from within Visual Studio, please visit

- ▶ [NVIDIA Nsight Integration Overview](#)
- ▶ [NVIDIA Nsight Integration User Guide](#)

# Chapter 26.

## TROUBLESHOOTING

### 26.1. General Troubleshooting

#### Profiling

If the profiler behaves unexpectedly during the profiling session, or the profiling session fails to start, try the following steps:

- ▶ Close the host application.
- ▶ Restart the target device.
- ▶ Start the host application and connect to the target device.

Nsight Systems uses a settings file (**NVIDIA Nsight Systems.ini**) on the host to store information about loaded projects, report files, window layout configuration, etc. Location of the settings file is described in the **Help # About** dialog. Deleting the settings file will restore Nsight Systems to a fresh state, but all projects and reports will disappear from the Project Explorer.

#### Environment Variables

By default, Nsight Systems writes temporary files to **/tmp** directory. If you are using a system that does not allow writing to **/tmp** or where the **/tmp** directory has limited storage you can use the **TMPDIR** environment variable to set a different location. An example:

```
TMPDIR=/testdata ./bin/nsys profile -t cuda matrixMul
```

Environment variable control support for Windows target trace is not available, but there is a quick workaround:

- ▶ Create a batch file that sets the env vars and launches your application.
- ▶ Set Nsight Systems to launch the batch file as its target, i.e. set the project settings target path to the path of batch file.
- ▶ Start the trace. Nsight Systems will launch the batch file in a new cmd instance and trace any child process it launches. In fact, it will trace the whole process tree whose root is the cmd running your batch file.

## WebGL Testing

Nsight Systems cannot profile using the default Chrome launch command. To profile WebGL please follow the following command structure:

```
"C:\Program Files (x86)\Google\Chrome\Application\chrome.exe"
--inprocess-gpu --no-sandbox --disable-gpu-watchdog --use-angle=gl
https://webglsamples.org/aquarium/aquarium.html
```

## Common Issues with QNX Targets

- ▶ Make sure that **tracelogger** utility is available and can be run on the target.
- ▶ Make sure that **/tmp** directory is accessible and supports sub-directories.
- ▶ When switching between Nsight Systems versions, processes related to the previous version, including profiled applications forked by the daemon, must be killed before the new version is used. If you experience issues after switching between Nsight Systems versions, try rebooting the target.

## 26.2. CLI Troubleshooting

If you have collected a report file using the CLI and the report will not open in the GUI, check to see that your GUI version is the same or greater than the CLI version you used. If it is not, download a new version of the Nsight Systems GUI and you will be able to load and visualize your report.

This situation occurs most frequently when you update Nsight Systems using a CLI only package, such as the package available from the NVIDIA HPC SDK.

## 26.3. Launch Processes in Stopped State

In many cases, it is important to profile an application from the very beginning of its execution. When launching processes, Nsight Systems takes care of it by making sure that the profiling session is fully initialized before making the **exec()** system call on Linux.

If the process launch capabilities of Nsight Systems are not sufficient, the application should be launched manually, and the profiler should be configured to attach to the already launched process. One approach would be to call **sleep()** somewhere early in the application code, which would provide time for the user to attach to the process in Nsight Systems Embedded Platforms Edition, but there are two other more convenient mechanisms that can be used on Linux, without the need to recompile the application. (Note that the rest of this section is only applicable to Linux-based target devices.)

Both mechanisms ensure that between the time the process is created (and therefore its PID is known) and the time any of the application's code is called, the process is stopped and waits for a signal to be delivered before continuing.

## LD\_PRELOAD

The first mechanism uses **LD\_PRELOAD** environment variable. It only works with dynamically linked binaries, since static binaries do not invoke the runtime linker, and therefore are not affected by the **LD\_PRELOAD** environment variable.

- ▶ For ARMv7 binaries, preload  
`/opt/nvidia/nsight_systems/libLauncher32.so`
- ▶ Otherwise if running from host, preload  
`/opt/nvidia/nsight_systems/libLauncher64.so`
- ▶ Otherwise if running from CLI, preload  
`[installation_directory]/libLauncher64.so`

The most common way to do that is to specify the environment variable as part of the process launch command, for example:

```
$ LD_PRELOAD=/opt/nvidia/nsight_systems/libLauncher64.so ./my-aarch64-binary --arguments
```

When loaded, this library will send itself a **SIGSTOP** signal, which is equivalent to typing **Ctrl+Z** in the terminal. The process is now a background job, and you can use standard commands like **jobs**, **fg** and **bg** to control them. Use **jobs -l** to see the PID of the launched process.

When attaching to a stopped process, Nsight Systems will send **SIGCONT** signal, which is equivalent to using the **bg** command.

## Launcher

The second mechanism can be used with any binary. Use **[installation\_directory]/launcher** to launch your application, for example:

```
$ /opt/nvidia/nsight_systems/launcher ./my-binary --arguments
```

The process will be launched, daemonized, and wait for **SIGUSR1** signal. After attaching to the process with Nsight Systems, the user needs to manually resume execution of the process from command line:

```
$ pkill -USR1 launcher
```

**Note:**

Note that **pkill** will send the signal to any process with the matching name. If that

```

is
not
desirable,
use
kill
to
send
it
to
a
specific
process.
The
standard
output
and
error
streams
are
redirected
to
/
tmp/
stdout_<PID>.txt
and
/
tmp/
stderr_<PID>.txt

```

The launcher mechanism is more complex and less automated than the LD\_PRELOAD option, but gives more control to the user.

## 26.4. GUI Troubleshooting

If opening the Nsight Systems Linux GUI fails with one of the following errors, you may be missing some required libraries:

```

This application failed to start because it could not find or load the Qt
platform plugin "xcb" in "". Available platform plugins are: xcb. Reinstalling
the application may fix this problem.

```

or

```

error while loading shared libraries: [library_name]: cannot open shared object
file: No such file or directory

```

## Ubuntu 18.04/20.04 and CentOS 7/8 with root privileges

- ▶ Launch the following command, which will install all the required libraries in system directories:
 

```
[installation_path]/host-linux-x64/Scripts/install-dependencies.sh
```
- ▶ Launch the Linux GUI as usual.

## Ubuntu 18.04/20.04 and CentOS 7/8 without root privileges

- ▶ Choose the directory where dependencies will be installed (**dependencies\_path**). This directory should be writeable for the current user.
- ▶ Launch the following command (if it has already been run, move to the next step), which will install all the required libraries in **[dependencies\_path]**:

```
[installation_path]/host-linux-x64/Scripts/install-dependencies-without-root.sh [dependencies_path]
```

- ▶ Further, use the following command to launch the Linux GUI:


```
source [installation_path]/host-linux-x64/Scripts/setup-dependencies-environment.sh [dependencies_path] && [installation_path]/host-linux-x64/nsys-ui
```

## Other platforms, or if the previous steps did not help

Launch Nsight Systems using the following command line to determine which libraries are missing and install them.

```
$ QT_DEBUG_PLUGINS=1 ./nsys-ui
```

If the workload does not run when launched via Nsight Systems or the timeline is empty, check the stderr.log and stdout.log (click on drop-down menu showing **Timeline View** and click on **Files**) to see the errors encountered by the app.



## 26.5. Symbol Resolution

If stack trace information is missing symbols and you have a symbol file, you can manually re-resolve using the ResolveSymbols utility. This can be done by right-clicking the report file in the Project Explorer window and selecting "Resolve Symbols...".

Alternatively, you can find the utility as a separate executable in the **[installation\_path]\Host** directory. This utility works with ELF format files, with Windows PDB directories and symbol servers, or with files where each line is in the format **<start><length><name>**.

Short	Long	Argument	Description
-h	--help		Help message providing information about available options.

Short	Long	Argument	Description
-l	--process-list		Print global process IDs list
-s	--sym-file	filename	Path to symbol file
-b	--base-addr	address	If set then <start> in symbol file is treated as relative address starting from this base address
-p	--global-pid	pid	Which process in the report should be resolved. May be omitted if there is only one process in the report.
-f	--force		This option forces use of a given symbol file.
-i	--report	filename	Path to the report with unresolved symbols.
-o	--output	filename	Path and name of the output file. If it is omitted then "resolved" suffix is added to the original filename.
-d	--directories	directory paths	List of symbol folder paths, separated by semi-colon characters. Available only on Windows.
-v	--servers	server URLs	List of symbol servers that uses the same format as <b>_NT_SYMBOL_PATH</b> environment variable, i.e. <b>srv*&lt;LocalStore&gt;*&lt;SymbolServer&gt;</b> . Available only on Windows.

Short	Long	Argument	Description
-n	--ignore-nt-sym-path		Ignore the symbol locations stored in the <code>_NT_SYMBOL_PATH</code> environment variable. Available only on Windows.

## Broken Backtraces on Tegra

In Nsight Systems Embedded Platforms Edition, in the symbols table there is a special entry called **Broken backtraces**. This entry is used to denote the point in the call chain where the unwinding algorithms used by Nsight Systems could not determine what is the next (caller) function.

Broken backtraces happen because there is no information related to the current function that the unwinding algorithms can use. In the Top-Down view, these functions are immediate children of the Broken backtraces row.

One can eliminate broken backtraces by modifying the build system to provide at least one kind of unwind information. The types of unwind information, used by the algorithms in Nsight Systems, include the following:

For ARMv7 binaries:

- ▶ DWARF information in ELF sections: `.debug_frame`, `.zdebug_frame`, `.eh_frame`, `.eh_frame_hdr`. This information is the most precise. `.zdebug_frame` is a compressed version of `.debug_frame`, so at most one of them is typically present. `.eh_frame_hdr` is a companion section for `.eh_frame` and might be absent.

Compiler flag: `-g`.

- ▶ Exception handling information in EHABI format provided in `.ARM.exidx` and `.ARM.exstab` ELF sections. `.ARM.exstab` might be absent if all information is compact enough to be encoded into `.ARM.exidx`.

Compiler flag: `-funwind-tables`.

- ▶ Frame pointers (built into the `.text` section).

Compiler flag: `-fno-omit-frame-pointer`.

For Aarch64 binaries:

- ▶ DWARF information in ELF sections: `.debug_frame`, `.zdebug_frame`, `.eh_frame`, `.eh_frame_hdr`. See additional comments above.

Compiler flag: `-g`.

- ▶ Frame pointers (built into the `.text` section).

Compiler flag: `-fno-omit-frame-pointer`.

The following ELF sections should be considered empty if they have size of 4 bytes: **.debug\_frame**, **.eh\_frame**, **.ARM.exidx**. In this case, these sections only contain termination records and no useful information.

For GCC, use the following compiler invocation to see which compiler flags are enabled in your toolchain by default (for example, to check if **-funwind-tables** is enabled by default):

```
$ gcc -Q --help=common
```

For GCC and Clang, add **-###** to the compiler invocation command to see which compiler flags are actually being used.

Since EHABI and DWARF information is compiled on per-unit basis (every **.cpp** or **.c** file, as well as every static library, can be built with or without this information), presence of the ELF sections does not guarantee that every function has necessary unwind information.

Frame pointers are required by the Aarch64 Procedure Call Standard. Adding frame pointers slows down execution time, but in most cases the difference is negligible.

## Debug Versions of ELF Files

Often, after a binary is built, especially if it is built with debug information (**-g** compiler flag), it gets stripped before deploying or installing. In this case, ELF sections that contain useful information, such as non-export function names or unwind information, can get stripped as well.

One solution is to deploy or install the original unstripped library instead of the stripped one, but in many cases this would be inconvenient. Nsight Systems can use missing information from alternative locations.

For target devices with Ubuntu, see [Debug Symbol Packages](#). These packages typically install debug ELF files with **/usr/lib/debug** prefix. Nsight Systems can find debug libraries there, and if it matches the original library (e.g., the built-in **BuildID** is the same), it will be picked up and used to provide symbol names and unwind information.

Many packages have debug companions in the same repository and can be directly installed with APT (**apt-get**). Look for packages with the **-dbg** suffix. For other packages, refer to the [Debug Symbol Packages](#) wiki page on how to add the debs package repository. After setting up the repository and running **apt-get update**, look for packages with **-dbgsym** suffix.

To verify that a debug version of a library has been picked up and downloaded from the target device, look in the **Module Summary** section of **Analysis Summary**:

Module summary		
Module name	Address	CPU time
[kernel.kallsyms]	0xffffffff000080000- 0xffffffff001471010	53.46%
/lib/aarch64-linux-gnu/libc-2.23.so	0x7f7ebad000-0x7f7ecda000	26.04%
/usr/lib/debug/lib/aarch64-linux-gnu/libc-2.23.so		

## 26.6. Logging

To enable logging on the host, refer to this config file:

```
host-linux-x64/nvlog.config.template
```

When reporting any bugs please include the build version number as described in the **Help # About** dialog. If possible, attach log files and report (**.nsys-rep**) files, as they already contain necessary version information.

### Verbose Logging on Linux Targets

Verbose logging is available when connecting to a Linux-based device from the GUI on the host. This extra debug information is not available when launching via the command line. Nsight Systems installs its executable and library files into the following directory:

```
/opt/nvidia/nsight_systems/
```

To enable verbose logging on the target device, when launched from the host, follow these steps:

1. Close the host application.
2. Restart the target device.
3. Place **nvlog.config** from host directory to the **/opt/nvidia/nsight\_systems** directory on target.
4. From SSH console, launch the following command:

```
sudo /opt/nvidia/nsight_systems/nsys --daemon --debug
```

5. Start the host application and connect to the target device.

Logs on the target devices are collected into this file (if enabled):

```
nsys.log
```

in the directory where **nsys** command was launched.

Please note that in some cases, debug logging can significantly slow down the profiler.

### Verbose Logging on Windows Targets

Verbose logging is available when connecting to a Windows-based device from the GUI on the host. Nsight Systems installs its executable and library files into the following directory by default:

```
C:\Program Files\NVIDIA Corporation\Nsight Systems 2022.1
```

To enable verbose logging on the target device, when launched from the host, follow these steps:

1. Close the host application.
2. Terminate the **nsys** process.
3. Place **nvlog.config** from host directory next to Nsight Systems Windows agent on the target device

- ▶ Local Windows target:

```
C:\Program Files\NVIDIA Corporation\Nsight Systems 2022.1\target-  
windows-x64
```

- ▶ Remote Windows target:

```
C:\Users\<user name>\AppData\Local\Temp\nvidia\nsight_systems
```

4. Start the host application and connect to the target device.

Logs on the target devices are collected into this file (if enabled):

```
nsight-sys.log
```

in the same directory as Nsight Systems Windows agent.

Please note that in some cases debug logging can significantly slow down the profiler.

# Chapter 27.

## OTHER RESOURCES

Looking for information to help you use Nsight Systems the most effectively? Here are some more resources you might want to review:

### Feature Videos

Short videos, only a minute or two, to introduce new features.

- ▶ [OpenMP Trace Feature Spotlight](#)
- ▶ [Command Line Sessions Video Spotlight](#)
- ▶ [Direct3D11 Feature Spotlight](#)
- ▶ [Vulkan Trace](#)
- ▶ [Statistics Driven Profiling](#)
- ▶ [Analyzing NCCL Usage with NVIDIA Nsight Systems](#)

### Blog Posts

NVIDIA developer blogs, these are longer form, technical pieces written by tool and domain experts.

- ▶ [2021 - Optimizing DX12 Resource Uploads to the GPU Using CPU-Visible VRAM](#)
- ▶ [2019 - Migrating to NVIDIA Nsight Tools from NVVP and nvprof](#)
- ▶ [2019 - Transitioning to Nsight Systems from NVIDIA Visual Profiler / nvprof](#)
- ▶ [2019 - NVIDIA Nsight Systems Add Vulkan Support](#)
- ▶ [2019 - TensorFlow Performance Logging Plugin nvtx-plugins-tf Goes Public](#)
- ▶ [2020 - NVIDIA Nsight Systems in Containers and the Cloud](#)
- ▶ [2020 - Understanding the Visualization of Overhead and Latency in Nsight Systems](#)
- ▶ [2021 - Optimizing DX12 Resource Uploads to the GPU Using CPU-Visible VRAM](#)

### Training Seminars

2018 NCSA Blue Waters Webinar - [Introduction to NVIDIA Nsight Systems](#)

## Conference Presentations

- ▶ GTC 2020 - Rebalancing the Load: Profile-Guided Optimization of the NAMD Molecular Dynamics Program for Modern GPUs using Nsight Systems
- ▶ GTC 2020 - Scaling the Transformer Model Implementation in PyTorch Across Multiple Nodes
- ▶ GTC 2019 - Using Nsight Tools to Optimize the NAMD Molecular Dynamics Simulation Program
- ▶ GTC 2019 - Optimizing Facebook AI Workloads for NVIDIA GPUs
- ▶ GTC 2018 - Optimizing HPC Simulation and Visualization Codes Using NVIDIA Nsight Systems
- ▶ GTC 2018 - Israel - Boost DNN Training Performance using NVIDIA Tools
- ▶ Siggraph 2018 - Taming the Beast; Using NVIDIA Tools to Unlock Hidden GPU Performance

## For More Support

To file a bug report or to ask a question on the Nsight Systems forums, you will need to register with the NVIDIA Developer Program. See the [FAQ](#). You do not need to register to read the forums.

After that, you can access Nsight Systems [Forums](#) and the [NVIDIA Bug Tracking System](#).

To submit feedback directly from the GUI, go to **Help->Send Feedback** and fill out the form. Enter your email address if you would like to hear back from the Nsight Systems team.



The screenshot shows a window titled "NVIDIA Nsight Systems" with a feedback form. The form has a dropdown menu set to "Feature Suggestion". Below it is a text area for comments with the placeholder "Please enter your feedback here...". There are three checkboxes: "Include System Info", "Include Screenshots", and "Attach Additional Files:", all of which are checked. Below these is a "Contact Information" section with input fields for "Name:" and "Email:". A paragraph of legal text follows, stating that by providing an email, the user agrees to contact from NVIDIA for software improvement purposes, and that they can request deletion of their feedback at devtools-support@nvidia.com. At the bottom right are "Send" and "Cancel" buttons.

**NVIDIA Nsight Systems**

**Feedback for NVIDIA Nsight Systems**

Feature Suggestion

Comments:

Please enter your feedback here...

☒ Include System Info

☒ Include Screenshots

☒ **Attach Additional Files:**

Contact Information:

Name: Email:

By providing your email, you agree that NVIDIA may contact you regarding this feedback. Information you upload will only be used for the purpose of improving NVIDIA software. Please do not include any personal data in your uploads. If you have provided your email, you may request to delete your feedback at devtools-support@nvidia.com at any time.

Send Cancel